PSBLAS 3.5.0 User's guide

A reference guide for the Parallel Sparse BLAS library

by Salvatore Filippone and Alfredo Buttari University of Rome "Tor Vergata".

Sep 1st, 2017

Contents

1	Intr	oduction	1
2	Gen	eral overview	2
	2.1	Basic Nomenclature	3
	2.2	Library contents	4
	2.3	· ·	6
			8
	2.4		8
3	Dat	a Structures and Classes	9
•	3.1		9
	0.1	3.1.1 Descriptor Methods	
		get_local_rows	
		get_local_cols	
		get_global_rows	
		get_global_cols	
		get_global_rows	
		get_context	
		Clone	
		CNV	
		psb_cd_get_large_threshold	
		psb_cd_set_large_threshold	
		3.1.2 Named Constants	
	3.2	Sparse Matrix class	
		3.2.1 Sparse Matrix Methods	
		get_nrows	б
		get_ncols	6
		get_nnzeros	7
		get_size	7
		sizeof	7
		get_fmt	8
		is_bld, is_upd, is_asb	8
		is_lower, is_upper, is_triangle, is_unit	8
		cscnv	9
		csclip	9
		clean_zeros	
		get_diag	
		clip_diag	
		tril	
		triu	
		psb_set_mat_default	
		clone	
		3.2.2 Named Constants	
	3.3	Dense Vector Data Structure	
	ა.ა		
		get_nrows	
			4

	$\operatorname{get_vect}$	$\frac{25}{26}$
	3.4 Preconditioner data structure	26
	3.5 Heap data structure	26
	5.5 Treap data structure	20
4	Computational routines	28
	psb_geaxpby	29
	psb_gedot	31
	psb_gedots	33
	psb_normi	35
	psb_geamaxs	36
	psb_norm1	37
	psb_geasums	38
	psb_norm2	40
	psb_genrm2s	41
	psb_norm1	42
	psb_normi	43
	psb_spmm	44
	psb_spsm	46
	pso-spoin	10
5	Communication routines	49
	psb_halo	50
	psb_ovrl	53
	psb_gather	57
	psb_scatter	59
	· · · · · · · · · · · · · · · · · · ·	
6	Data management routines	61
6	Data management routines psb_cdall	61
6	The state of the s	
6	psb_cdall	61
6	psb_cdall	61 65
6	psb_cdall	61 65 67
6	psb_cdall	61 65 67 68
6	psb_cdall	61 65 67 68
6	psb_cdall	61 65 67 68 69 70
6	psb_cdall	61 65 67 68 69 70
6	psb_cdall	61 65 67 68 69 70 72 73
6	psb_cdall . psb_cdins psb_cdasb . psb_cdcpy psb_cdfree . psb_cdbldext psb_spall . psb_spins psb_spasb . psb_spfree .	61 65 67 68 69 70 72 73
6	psb_cdall . psb_cdins psb_cdasb . psb_cdcpy psb_cdfree . psb_cdbldext psb_spall . psb_spins psb_spasb . psb_spfree psb_sprn . psb_sprn .	61 65 67 68 69 70 72 73 75
6	psb_cdall . psb_cdins psb_cdasb . psb_cdcpy psb_cdfree . psb_cdbldext psb_spall . psb_spins psb_spins . psb_spesb psb_spfree . psb_sprn psb_geall . psb_geall .	61 65 67 68 69 70 72 73 75 77
6	psb_cdall . psb_cdins psb_cdasb . psb_cdcpy psb_cdfree . psb_cdbldext psb_spall . psb_spins . psb_spins . psb_spire . psb_spfree . psb_sprn . psb_geall . psb_geins .	61 65 67 68 69 70 72 73 75 77
6	psb_cdall . psb_cdins psb_cdasb . psb_cdcpy psb_cdfree . psb_cdbldext psb_spall . psb_spins . psb_spins . psb_spses . psb_spfree . psb_sprn . psb_geall . psb_geins . psb_geasb . psb_geasb .	61 65 67 68 69 70 72 73 75 77 78 80 82
6	psb_cdall	61 65 67 68 69 70 72 73 75 77 78 80
6	psb_cdall	61 65 67 68 69 70 72 73 75 77 78 80 82 83 84
6	psb_cdall	61656666666666666666666666666666666666
6	psb_cdall	61656567668669700727375577788082883844855877
6	psb_cdall	61656768866997072737587798082283884855888
6	psb_cdall . psb_cdins psb_cdasb psb_cdcpy psb_cdfree psb_cdbldext psb_spall . psb_spins psb_spasb . psb_spfree psb_sprn . psb_geall . psb_geall . psb_geins psb_geins psb_geins psb_geins psb_geins psb_geins psb_geins psb_gefree psb_gelp . psb_glob_to_loc psb_loc_to_glob psb_is_owned psb_owned_index	61656768866997072737577788082283384485588888888
6	psb_cdall . psb_cdasb psb_cdasb psb_cdcpy psb_cdfree psb_cdbldext psb_spall . psb_spins psb_spins psb_spfree psb_spfree psb_sprn psb_geall . psb_geals psb_geins psb_geins psb_geins psb_gelp psb_glob_to_loc psb_loc_to_glob psb_is_owned psb_owned_index psb_is_local	611 655 677 688 699 707 727 737 757 778 808 828 838 844 858 878 888 899 900
6	psb_cdall . psb_cdins psb_cdasb psb_cdcpy psb_cdfree psb_cdbldext psb_spall . psb_spins psb_spasb . psb_spfree psb_sprn . psb_geall . psb_geall . psb_geins psb_geins psb_geins psb_geins psb_geins psb_geins psb_geins psb_gefree psb_gelp . psb_glob_to_loc psb_loc_to_glob psb_is_owned psb_owned_index	61656768866997072737577788082283384485588888888

	psb_get_overlap	93
	psb_sp_getrow	94
	psb_sizeof	96
	Sorting utilities	97
	Ŭ	
7	Parallel environment routines	99
	psb_init	100
	psb_info	101
	psb_exit	102
	psb_get_mpicomm	103
	psb_get_rank	104
	psb_wtime	105
	psb_barrier	106
	psb_abort	107
	psb_bcast	108
	psb_sum	109
	psb_max	
	psb_min	
	psb_amx	
	psb_amn	
	psb_snd	
	psb_rcv	
	positiv	110
8	Error handling	116
	psb_errpush	118
	psb_error	119
	psb_set_errverbosity	
	psb_set_erraction	
9	Utilities	122
	hb_read	
		124
	mm_mat_read	125
	mm_array_read	126
	mm_mat_write	127
	$mm_array_write \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	128
10		129
	prec%init	130
	prec%build	131
	prec%apply	133
	prec%descr	
	clone	135
	prec%free	136
	To the Notation	10-
11		137
	psb_krylov	138

1 Introduction

The PSBLAS library, developed with the aim to facilitate the parallelization of computationally intensive scientific applications, is designed to address parallel implementation of iterative solvers for sparse linear systems through the distributed memory paradigm. It includes routines for multiplying sparse matrices by dense matrices, solving block diagonal systems with triangular diagonal entries, preprocessing sparse matrices, and contains additional routines for dense matrix operations. The current implementation of PSBLAS addresses a distributed memory execution model operating with message passing.

The PSBLAS library version 3 is implemented in the Fortran 2003 [17] programming language, with reuse and/or adaptation of existing Fortran 77 and Fortran 95 software, plus a handful of C routines.

The use of Fortran 2003 offers a number of advantages over Fortran 95, mostly in the handling of requirements for evolution and adaptation of the library to new computing architectures and integration of new algorithms. For a detailed discussion of our design see [11]; other works discussing advanced programming in Fortran 2003 include [1, 18]; sufficient support for Fortran 2003 is now available from many compilers, including the GNU Fortran compiler from the Free Software Foundation (as of version 4.8).

Previous approaches have been based on mixing Fortran 95, with its support for object-based design, with other languages; these have been advocated by a number of authors, e.g. [16]. Moreover, the Fortran 95 facilities for dynamic memory management and interface overloading greatly enhance the usability of the PSBLAS subroutines. In this way, the library can take care of runtime memory requirements that are quite difficult or even impossible to predict at implementation or compilation time.

The presentation of the PSBLAS library follows the general structure of the proposal for serial Sparse BLAS [8, 9], which in its turn is based on the proposal for BLAS on dense matrices [15, 5, 6].

The applicability of sparse iterative solvers to many different areas causes some terminology problems because the same concept may be denoted through different names depending on the application area. The PSBLAS features presented in this document will be discussed referring to a finite difference discretization of a Partial Differential Equation (PDE). However, the scope of the library is wider than that: for example, it can be applied to finite element discretizations of PDEs, and even to different classes of problems such as nonlinear optimization, for example in optimal control problems.

The design of a solver for sparse linear systems is driven by many conflicting objectives, such as limiting occupation of storage resources, exploiting regularities in the input data, exploiting hardware characteristics of the parallel platform. To achieve an optimal communication to computation ratio on distributed memory machines it is essential to keep the *data locality* as high as possible; this can be done through an appropriate data allocation strategy. The choice of the preconditioner is another very important factor that affects efficiency of the implemented application. Optimal data distribution requirements for a given preconditioner may conflict with distribution requirements of the rest of the solver. Finding the optimal trade-off may be very difficult because it is application dependent. Possible solutions to these problems and other important inputs to the development of the PSBLAS software package

have come from an established experience in applying the PSBLAS solvers to computational fluid dynamics applications.

2 General overview

The PSBLAS library is designed to handle the implementation of iterative solvers for sparse linear systems on distributed memory parallel computers. The system coefficient matrix A must be square; it may be real or complex, nonsymmetric, and its sparsity pattern needs not to be symmetric. The serial computation parts are based on the serial sparse BLAS, so that any extension made to the data structures of the serial kernels is available to the parallel version. The overall design and parallelization strategy have been influenced by the structure of the ScaLAPACK parallel library. The layered structure of the PSBLAS library is shown in figure 1; lower layers of the library indicate an encapsulation relationship with upper layers. The ongoing discussion focuses on the Fortran 2003 layer immediately below the application layer. The serial parts of the computation on each process are executed through calls to the serial sparse BLAS subroutines. In a similar way, the inter-process message exchanges are encapsulated in an application layer that has been strongly inspired by the Basic Linear Algebra Communication Subroutines (BLACS) library [7]. Usually there is no need to deal directly with MPI; however, in some cases, MPI routines are used directly to improve efficiency. For further details on our communication layer see Sec. 7.




Figure 1: PSBLAS library components hierarchy.

The type of linear system matrices that we address typically arise in the numerical solution of PDEs; in such a context, it is necessary to pay special attention to the structure of the problem from which the application originates. The nonzero pattern of a matrix arising from the discretization of a PDE is influenced by various factors, such as the shape of the domain, the discretization strategy, and the equation/unknown ordering. The matrix itself can be interpreted as the adjacency matrix of the graph associated with the discretization mesh.

The distribution of the coefficient matrix for the linear system is based on the "owner computes" rule: the variable associated to each mesh point is assigned

to a process that will own the corresponding row in the coefficient matrix and will carry out all related computations. This allocation strategy is equivalent to a partition of the discretization mesh into *sub-domains*. Our library supports any distribution that keeps together the coefficients of each matrix row; there are no other constraints on the variable assignment. This choice is consistent with simple data distributions such as CYCLIC(N) and BLOCK, as well as completely arbitrary assignments of equation indices to processes. In particular it is consistent with the usage of graph partitioning tools commonly available in the literature, e.g. METIS [14]. Dense vectors conform to sparse matrices, that is, the entries of a vector follow the same distribution of the matrix rows.

We assume that the sparse matrix is built in parallel, where each process generates its own portion. We never require that the entire matrix be available on a single node. However, it is possible to hold the entire matrix in one process and distribute it explicitly¹, even though the resulting memory bottleneck would make this option unattractive in most cases.

2.1 Basic Nomenclature

Our computational model implies that the data allocation on the parallel distributed memory machine is guided by the structure of the physical model, and specifically by the discretization mesh of the PDE.

Each point of the discretization mesh will have (at least) one associated equation/variable, and therefore one index. We say that point i depends on point j if the equation for a variable associated with i contains a term in j, or equivalently if $a_{ij} \neq 0$. After the partition of the discretization mesh into sub-domains assigned to the parallel processes, we classify the points of a given sub-domain as following.

Internal. An internal point of a given domain depends only on points of the same domain. If all points of a domain are assigned to one process, then a computational step (e.g., a matrix-vector product) of the equations associated with the internal points requires no data items from other domains and no communications.

Boundary. A point of a given domain is a boundary point if it *depends* on points belonging to other domains.

Halo. A halo point for a given domain is a point belonging to another domain such that there is a boundary point which depends on it. Whenever performing a computational step, such as a matrix-vector product, the values associated with halo points are requested from other domains. A boundary point of a given domain is usually a halo point for some other domain²; therefore the cardinality of the boundary points set denotes the amount of data sent to other domains.

¹In our prototype implementation we provide sample scatter/gather routines.

²This is the normal situation when the pattern of the sparse matrix is symmetric, which is equivalent to say that the interaction between two variables is reciprocal. If the matrix pattern is non-symmetric we may have one-way interactions, and these could cause a situation in which a boundary point is not a halo point for its neighbour.

Overlap. An overlap point is a boundary point assigned to multiple domains. Any operation that involves an overlap point has to be replicated for each assignment.

Overlap points do not usually exist in the basic data distributions; however they are a feature of Domain Decomposition Schwarz preconditioners which are the subject of related research work [4, 3].

We denote the sets of internal, boundary and halo points for a given subdomain by \mathcal{I} , \mathcal{B} and \mathcal{H} . Each subdomain is assigned to one process; each process usually owns one subdomain, although the user may choose to assign more than one subdomain to a process. If each process i owns one subdomain, the number of rows in the local sparse matrix is $|\mathcal{I}_i| + |\mathcal{B}_i|$, and the number of local columns (i.e. those for which there exists at least one non-zero entry in the local rows) is $|\mathcal{I}_i| + |\mathcal{B}_i| + |\mathcal{H}_i|$.




Figure 2: Point classification.

This classification of mesh points guides the naming scheme that we adopted in the library internals and in the data structures. We explicitly note that "Halo" points are also often called "ghost" points in the literature.

2.2 Library contents

The PSBLAS library consists of various classes of subroutines:

Computational routines comprising:

- Sparse matrix by dense matrix product;
- Sparse triangular systems solution for block diagonal matrices;
- Vector and matrix norms;
- Dense matrix sums;
- Dot products.

Communication routines handling halo and overlap communications;

Data management and auxiliary routines including:

- Parallel environment management
- Communication descriptors allocation;
- Dense and sparse matrix allocation;
- Dense and sparse matrix build and update;
- Sparse matrix and data distribution preprocessing.

Preconditioner routines

Iterative methods a subset of Krylov subspace iterative methods

The following naming scheme has been adopted for all the symbols internally defined in the PSBLAS software package:

- all symbols (i.e. subroutine names, data types...) are prefixed by psb_
- all data type names are suffixed by _type
- all constants are suffixed by _
- all top-level subroutine names follow the rule psb_xxname where xx can be either:
 - ge: the routine is related to dense data,
 - sp: the routine is related to sparse data,
 - cd: the routine is related to communication descriptor (see 3).

For example the psb_geins, psb_spins and psb_cdins perform the same action (see 6) on dense matrices, sparse matrices and communication descriptors respectively. Interface overloading allows the usage of the same subroutine names for both real and complex data.

In the description of the subroutines, arguments or argument entries are classified as:

global For input arguments, the value must be the same on all processes participating in the subroutine call; for output arguments the value is guaranteed to be the same.

local Each process has its own value(s) independently.

To finish our general description, we define a version string with the constant

psb_version_string_

whose current value is 3.4.0

2.3 Application structure

The main underlying principle of the PSBLAS library is that the library objects are created and exist with reference to a discretized space to which there corresponds an index space and a matrix sparsity pattern. As an example, consider a cell-centered finite-volume discretization of the Navier-Stokes equations on a simulation domain; the index space $1 \dots n$ is isomorphic to the set of cell centers, whereas the pattern of the associated linear system matrix is isomorphic to the adjacency graph imposed on the discretization mesh by the discretization stencil.

Thus the first order of business is to establish an index space, and this is done with a call to psb_cdall in which we specify the size of the index space n and the allocation of the elements of the index space to the various processes making up the MPI (virtual) parallel machine.

The index space is partitioned among processes, and this creates a mapping from the "global" numbering $1 \dots n$ to a numbering "local" to each process; each process i will own a certain subset $1 \dots n_{\text{TOW}i}$, each element of which corresponds to a certain element of $1 \dots n$. The user does not set explicitly this mapping; when the application needs to indicate to which element of the index space a certain item is related, such as the row and column index of a matrix coefficient, it does so in the "global" numbering, and the library will translate into the appropriate "local" numbering.

For a given index space $1\ldots n$ there are many possible associated topologies, i.e. many different discretization stencils; thus the description of the index space is not completed until the user has defined a sparsity pattern, either explicitly through psb_cdins or implicitly through psb_spins. The descriptor is finalized with a call to psb_cdasb and a sparse matrix with a call to psb_spasb. After psb_cdasb each process i will have defined a set of "halo" (or "ghost") indices $n_{\text{TOW}_i} + 1 \ldots n_{\text{col}_i}$, denoting elements of the index space that are not assigned to process i; however the variables associated with them are needed to complete computations associated with the sparse matrix A, and thus they have to be fetched from (neighbouring) processes. The descriptor of the index space is built exactly for the purpose of properly sequencing the communication steps required to achieve this objective.

A simple application structure will walk through the index space allocation, matrix/vector creation and linear system solution as follows:

- 1. Initialize parallel environment with psb_init
- 2. Initialize index space with psb_cdall
- 3. Allocate sparse matrix and dense vectors with psb_spall and psb_geall
- 4. Loop over all local rows, generate matrix and vector entries, and insert them with psb_spins and psb_geins
- 5. Assemble the various entities:
 - (a) psb_cdasb
 - (b) psb_spasb
 - (c) psb_geasb

- Choose the preconditioner to be used with prec%init and build it with prec%build³.
- 7. Call the iterative method of choice, e.g. psb_bicgstab

This is the structure of the sample program test/pargen/ppde.f90.

For a simulation in which the same discretization mesh is used over multiple time steps, the following structure may be more appropriate:

- 1. Initialize parallel environment with psb_init
- 2. Initialize index space with psb_cdall
- 3. Loop over the topology of the discretization mesh and build the descriptor with psb_cdins
- 4. Assemble the descriptor with psb_cdasb
- 5. Allocate the sparse matrices and dense vectors with psb_spall and psb_geall
- 6. Loop over the time steps:
 - (a) If after first time step, reinitialize the sparse matrix with psb_sprn; also zero out the dense vectors;
 - (b) Loop over the mesh, generate the coefficients and insert/update them with psb_spins and psb_geins
 - (c) Assemble with psb_spasb and psb_geasb
 - (d) Choose and build preconditioner with prec%init and prec%build
 - (e) Call the iterative method of choice, e.g. psb_bicgstab

The insertion routines will be called as many times as needed; they only need to be called on the data that is actually allocated to the current process, i.e. each process generates its own data.

In principle there is no specific order in the calls to psb_spins, nor is there a requirement to build a matrix row in its entirety before calling the routine; this allows the application programmer to walk through the discretization mesh element by element, generating the main part of a given matrix row but also contributions to the rows corresponding to neighbouring elements.

From a functional point of view it is even possible to execute one call for each nonzero coefficient; however this would have a substantial computational overhead. It is therefore advisable to pack a certain amount of data into each call to the insertion routine, say touching on a few tens of rows; the best performing value would depend on both the architecture of the computer being used and on the problem structure. At the opposite extreme, it would be possible to generate the entire part of a coefficient matrix residing on a process and pass it in a single call to psb_spins; this, however, would entail a doubling of memory occupation, and thus would be almost always far from optimal.

 $^{^3}$ The subroutine style $psb_precinit$ and psb_precbl are still supported for backward compatibility

2.3.1 User-defined index mappings

PSBLAS supports user-defined global to local index mappings, subject to the constraints outlined in sec. 2.3:

- 1. The set of indices owned locally must be mapped to the set $1 \dots n_{row_s}$;
- 2. The set of halo points must be mapped to the set $n_{row_i} + 1 \dots n_{col_i}$;

but otherwise the mapping is arbitrary. The user application is responsible to ensure consistency of this mapping; some errors may be caught by the library, but this is not guaranteed. The application structure to support this usage is as follows:

- 1. Initialize index space with psb_cdall(ictx,desc,info,vl=vl,lidx=lidx) passing the vectors vl(:) containing the set of global indices owned by the current process and lidx(:) containing the corresponding local indices;
- 2. Add the halo points ja(:) and their associated local indices lidx(:) with a(some) call(s) to psb_cdins(nz,ja,desc,info,lidx=lidx);
- 3. Assemble the descriptor with psb_cdasb;
- 4. Build the sparse matrices and vectors, optionally making use in psb_spins and psb_geins of the local argument specifying that the indices in ia, ja and irw, respectively, are already local indices.

2.4 Programming model

The PSBLAS librarary is based on the Single Program Multiple Data (SPMD) programming model: each process participating in the computation performs the same actions on a chunk of data. Parallelism is thus data-driven.

Because of this structure, many subroutines coordinate their action across the various processes, thus providing an implicit synchronization point, and therefore *must* be called simultaneously by all processes participating in the computation. This is certainly true for the data allocation and assembly routines, for all the computational routines and for some of the tools routines.

However there are many cases where no synchronization, and indeed no communication among processes, is implied; for instance, all the routines in sec. 3 are only acting on the local data structures, and thus may be called independently. The most important case is that of the coefficient insertion routines: since the number of coefficients in the sparse and dense matrices varies among the processors, and since the user is free to choose an arbitrary order in building the matrix entries, these routines cannot imply a synchronization.

Throughout this user's guide each subroutine will be clearly indicated as:

Synchronous: must be called simultaneously by all the processes in the relevant communication context;

Asynchronous: may be called in a totally independent manner.

3 Data Structures and Classes

In this chapter we illustrate the data structures used for definition of routines interfaces. They include data structures for sparse matrices, communication descriptors and preconditioners.

All the data types and the basic subroutine interfaces related to descriptors and sparse matrices are defined in the module psb_base_mod; this will have to be included by every user subroutine that makes use of the library. The preconditioners are defined in the module psb_prec_mod

Integer, real and complex data types are parametrized with a kind type defined in the library as follows:

- psb_spk_ Kind parameter for short precision real and complex data; corresponds to a REAL declaration and is normally 4 bytes;
- psb_dpk_ Kind parameter for long precision real and complex data; corresponds to a DOUBLE PRECISION declaration and is normally 8 bytes;
- **psb_ipk_** Kind parameter for integer data; with default build options this is a 4 bytes integer, but there is (highly) experimental support for 8-bytes integers;
- psb_mpik_ Kind parameter for 4-bytes integer data, as is always used by MPI;
- psb_long_int_k_ Kind parameter for long (8 bytes) integers, which are always used by the sizeof methods.

Together with the classes attributes we also discuss their methods. Most methods detailed here only act on the local variable, i.e. their action is purely local and asynchronous unless otherwise stated. The list of methods here is not completely exhaustive; many methods, especially those that alter the contents of the various objects, are usually not needed by the end-user, and therefore are described in the developer's documentation.

3.1 Descriptor data structure

All the general matrix informations and elements to be exchanged among processes are stored within a data structure of the type psb_desc_type. Every structure of this type is associated with a discretization pattern and enables data communications and other operations that are necessary for implementing the various algorithms of interest to us.

The data structure itself psb_desc_type can be treated as an opaque object handled via the tools routines of Sec. 6 or the query routines detailed below; nevertheless we include here a description for the curious reader.

First we describe the psb_indx_map type. This is a data structure that keeps track of a certain number of basic issues such as:

- The value of the communication/MPI context;
- The number of indices in the index space, i.e. global number of rows and columns of a sparse matrix;
- The local set of indices, including:

- The number of local indices (and local rows);
- The number of halo indices (and therefore local columns);
- The global indices corresponding to the local ones.

There are many different schemes for storing these data; therefore there are a number of types extending the base one, and the descriptor structure holds a polymorphic object whose dynamic type can be any of the extended types. The methods associated with this data type answer the following queries:

- For a given set of local indices, find the corresponding indices in the global numbering;
- For a given set of global indices, find the corresponding indices in the local numbering, if any, or return an invalid
- Add a global index to the set of halo indices;
- Find the process owner of each member of a set of global indices.

All methods but the last are purely local; the last method potentially requires communication among processes, and thus is a synchronous method. The choice of a specific dynamic type for the index map is made at the time the descriptor is initially allocated, according to the mode of initialization (see also 6).

The descriptor contents are as follows:

indxmap A polymorphic variable of a type that is any extension of the indx_map type described above.

halo_index A list of the halo and boundary elements for the current process to be exchanged with other processes; for each processes with which it is necessary to communicate:

- 1. Process identifier;
- 2. Number of points to be received;
- 3. Indices of points to be received;
- 4. Number of points to be sent;
- 5. Indices of points to be sent;

Specified as: a vector of integer type, see 3.3.

ext_index A list of element indices to be exchanged to implement the mapping between a base descriptor and a descriptor with overlap.

Specified as: a vector of integer type, see 3.3.

ovrlap_index A list of the overlap elements for the current process, organized in groups like the previous vector:

- 1. Process identifier;
- 2. Number of points to be received;
- 3. Indices of points to be received;
- 4. Number of points to be sent;

5. Indices of points to be sent;

Specified as: a vector of integer type, see 3.3.

ovr_mst_idx A list to retrieve the value of each overlap element from the respective master process.

Specified as: a vector of integer type, see 3.3.

ovrlap_elem For all overlap points belonging to the current process:

- 1. Overlap point index;
- 2. Number of processes sharing that overlap points;
- 3. Index of a "master" process:

Specified as: an allocatable integer array of rank two.

bnd_elem A list of all boundary points, i.e. points that have a connection with other processes.

The Fortran 2003 declaration for psb_desc_type structures is as follows: A

```
type psb_desc_type
    class(psb_indx_map), allocatable :: indxmap
    type(psb_i_vect_type) :: v_halo_index
    type(psb_i_vect_type) :: v_ext_index
    type(psb_i_vect_type) :: v_ovrlap_index
    type(psb_i_vect_type) :: v_ovr_mst_idx
    integer, allocatable :: ovrlap_elem(:,:)
    integer, allocatable :: bnd_elem(:)
end type psb_desc_type
```

Figure 3: The PSBLAS defined data type that contains the communication descriptor.

communication descriptor associated with a sparse matrix has a state, which can take the following values:

Build: State entered after the first allocation, and before the first assembly; in this state it is possible to add communication requirements among different processes.

Assembled: State entered after the assembly; computations using the associated sparse matrix, such as matrix-vector products, are only possible in this state.

3.1.1 Descriptor Methods

```
get_local_rows — Get number of local rows
nr = desc%get_local_rows()
Type: Asynchronous.
```

desc the communication descriptor.

Scope: local.

On Return

Function value The number of local rows, i.e. the number of rows owned by the current process; as explained in 1, it is equal to $|\mathcal{I}_i| + |\mathcal{B}_i|$. The returned value is specific to the calling process.

```
get_local_cols — Get number of local cols
```

```
nc = desc%get_local_cols()
```

Type: Asynchronous.

On Entry

desc the communication descriptor.

Scope: local.

On Return

Function value The number of local cols, i.e. the number of indices used by the current process, including both local and halo indices; as explained in 1, it is equal to $|\mathcal{I}_i| + |\mathcal{B}_i| + |\mathcal{H}_i|$. The returned value is specific to the calling process.

```
{\tt get\_global\_rows} - {\tt Get} \ {\tt number} \ {\tt of} \ {\tt global} \ {\tt rows}
```

```
nr = desc%get_global_rows()
```

Type: Asynchronous.

On Entry

desc the communication descriptor.

Scope: local.

On Return

Function value The number of global rows, i.e. the size of the global index space.

```
get_global_cols — Get number of global cols
```

```
nr = desc%get_global_cols()
```

Type: Asynchronous.

```
desc the communication descriptor. Scope: local.
```

On Return

Function value The number of global cols; usually this is equal to the number of global rows.

```
myidx = desc%get_global_indices([owned])
```

Type: Asynchronous.

On Entry

desc the communication descriptor.

Scope: **local**. Type: **required**.

owned Choose if you only want owned indices (owned=.true.) or also halo indices (owned=.false.). Scope: local.

Type: optional; default: .true..

On Return

Function value The global indices, returned as an allocatable integer array of rank 1.

get_context — Get communication context

```
ictxt = desc%get_context()
```

Type: Asynchronous.

On Entry

 $\mathbf{desc}\,$ the communication descriptor.

Scope: local.

On Return

Function value The communication context.

Clone — clone current object

call desc%clone(descout,info)

Type: Asynchronous.

desc the communication descriptor.

Scope: local.

On Return

descout A copy of the input object.

info Return code.

CNV — convert internal storage format

call desc%cnv(mold)

Type: Asynchronous.

On Entry

desc the communication descriptor.

Scope: local.

mold the desred integer storage format.

Scope: local.

Specified as: a object of type derived from (integer) psb_T_base_vect_type.

The mold arguments may be employed to interface with special devices, such as GPUs and other accelerators.

$psb_cd_get_large_threshold --- Get\ threshold\ for\ index\ mapping\ switch$

```
ith = psb_cd_get_large_threshold()
```

Type: Asynchronous.

On Return

Function value The current value for the size threshold.

$psb_cd_set_large_threshold$ — Set threshold for index mapping switch

```
call psb_cd_set_large_threshold(ith)
```

Type: Synchronous.

On Entry

ith the new threshold for communication descriptors.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer value greater than zero.

Note: the threshold value is only queried by the library at the time a call to psb_cdall is executed, therefore changing the threshold has no effect on communication descriptors that have already been initialized. Moreover the threshold must have the same value on all processes.

3.1.2 Named Constants

```
psb_none_ Generic no-op;
psb_root_ Default root process for broadcast and scatter operations;
psb_nohalo_ Do not fetch halo elements;
psb_halo_ Fetch halo elements from neighbouring processes;
psb_sum_ Sum overlapped elements
psb_avg_ Average overlapped elements
psb_comm_halo_ Exchange data based on the halo_index list;
psb_comm_ext_ Exchange data based on the ext_index list;
psb_comm_ovr_ Exchange data based on the ovrlap_index list;
psb_comm_mov_ Exchange data based on the ovrlap_index list;
```

3.2 Sparse Matrix class

The psb_Tspmat_type class contains all information about the local portion of the sparse matrix and its storage mode. Its design is based on the STATE design pattern [13] as detailed in [11]; the type declaration is shown in figure 4 where T is a placeholder for the data type and precision variants

- S Single precision real;
- **D** Double precision real;
- C Single precision complex;
- **Z** Double precision complex.

The actual data is contained in the polymorphic component a%a of type psb_T_base_sparse_mat; its specific layout can be chosen dynamically among the predefined types, or an entirely new storage layout can be implemented and passed to the library at runtime via the psb_spasb routine. The following very common formats are

```
type :: psb_Tspmat_type
  class(psb_T_base_sparse_mat), allocatable :: a
end type psb_Tspmat_type
```

Figure 4: The PSBLAS defined data type that contains a sparse matrix.

precompiled in PSBLAS and thus are always available:

```
psb_T_coo_sparse_mat Coordinate storage;
psb_T_csr_sparse_mat Compressed storage by rows;
psb_T_csc_sparse_mat Compressed storage by columns;
```

The inner sparse matrix has an associated state, which can take the following values:

Build: State entered after the first allocation, and before the first assembly; in this state it is possible to add nonzero entries.

Assembled: State entered after the assembly; computations using the sparse matrix, such as matrix-vector products, are only possible in this state;

Update: State entered after a reinitalization; this is used to handle applications in which the same sparsity pattern is used multiple times with different coefficients. In this state it is only possible to enter coefficients for already existing nonzero entries.

The only storage variant supporting the build state is COO; all other variants are obtained by conversion to/from it.

3.2.1 Sparse Matrix Methods

get_nrows — Get number of rows in a sparse matrix

nr = a%get_nrows()

Type: Asynchronous.

On Entry

a the sparse matrix Scope: **local**

On Return

Function value The number of rows of sparse matrix a.

get_ncols — Get number of columns in a sparse matrix

nc = a%get_ncols()

Type: Asynchronous.

On Entry

a the sparse matrix Scope: **local**

On Return

Function value The number of columns of sparse matrix a.

get_nnzeros — Get number of nonzero elements in a sparse matrix

```
nz = a%get_nnzeros()
```

Type: Asynchronous.

On Entry

a the sparse matrix Scope: **local**

On Return

Function value The number of nonzero elements stored in sparse matrix a.

Notes

1. The function value is specific to the storage format of matrix a; some storage formats employ padding, thus the returned value for the same matrix may be different for different storage choices.

 $\operatorname{get_size}$ — Get maximum number of nonzero elements in a sparse matrix

```
maxnz = a%get_size()
```

Type: Asynchronous.

On Entry

a the sparse matrix Scope: local

On Return

Function value The maximum number of nonzero elements that can be stored in sparse matrix **a** using its current memory allocation.

sizeof — Get memory occupation in bytes of a sparse matrix

```
memory_size = a%sizeof()
```

Type: Asynchronous.

On Entry

a the sparse matrix Scope: local

On Return

Function value The memory occupation in bytes.

On Return

Function value A short string describing the dynamic type of the matrix. Predefined values include NULL, COO, CSR and CSC.

is_bld, is_upd, is_asb — Status check

```
if (a%is_bld()) then
if (a%is_upd()) then
if (a%is_asb()) then
```

Type: Asynchronous.

On Entry

a the sparse matrix Scope: **local**

On Return

Function value A logical value indicating whether the matrix is in the Build, Update or Assembled state, respectively.

is_lower, is_upper, is_triangle, is_unit — Format check

```
if (a%is_triangle()) then
if (a%is_upper()) then
if (a%is_lower()) then
if (a%is_unit()) then
```

Type: Asynchronous.

On Entry

a the sparse matrix Scope: **local**

On Return

Function value A logical value indicating whether the matrix is triangular; if is_triangle() returns .true. check also if it is lower, upper and with a unit (i.e. assumed) diagonal.

cscnv — Convert to a different storage format

```
call a%cscnv(b,info [, type, mold, dupl])
call a%cscnv(info [, type, mold, dupl])
```

Type: Asynchronous.

On Entry

a the sparse matrix.

A variable of type psb_Tspmat_type.

Scope: local.

type a string requesting a new format.

Type: optional.

mold a variable of class(psb_T_base_sparse_mat) requesting a new format. Type: optional.

dupl an integer value specifing how to handle duplicates (see Named Constants below)

On Return

b,a A copy of a with a new storage format.

A variable of type psb_Tspmat_type.

info Return code.

The mold arguments may be employed to interface with special devices, such as GPUs and other accelerators.

csclip — Reduce to a submatrix

Returns the submatrix A(imin:imax,jmin:jmax), optionally rescaling row/col indices to the range 1:imax-imin+1,1:jmax-jmin+1.

Type: Asynchronous.

On Entry

 ${\bf a}\,$ the sparse matrix.

A variable of type psb_Tspmat_type.

Scope: local.

imin,imax,jmin,jmax Minimum and maximum row and column indices.

Type: optional.

rscale,cscale Whether to rescale row/column indices. Type: optional.

On Return

b A copy of a submatrix of **a**.

A variable of type psb_Tspmat_type.

info Return code.

clean_zeros — Eliminate zero coefficients

```
call a%clean_zeros(info)
```

Eliminates zero coefficients in the input matrix. Note that depending on the internal storage format, there may still be some amount of zero padding in the output.

Type: Asynchronous.

On Entry

a the sparse matrix.

A variable of type psb_Tspmat_type. Scope: local.

On Return

a The matrix a without zero coefficients.

A variable of type psb_Tspmat_type.

info Return code.

$get_diag - Get main diagonal$

```
call a%get_diag(d,info)
```

Returns a copy of the main diagonal.

Type: Asynchronous.

On Entry

a the sparse matrix.

A variable of type psb_Tspmat_type.

Scope: local.

On Return

d A copy of the main diagonal.

A one-dimensional array of the appropriate type.

info Return code.

clip_diag — Cut out main diagonal

```
call a%clip_diag(b,info)
```

Returns a copy of a without the main diagonal.

Type: Asynchronous.

On Entry

a the sparse matrix.

A variable of type psb_Tspmat_type. Scope: local.

On Return

b A copy of a without the main diagonal. A variable of type psb_Tspmat_type.

info Return code.

tril — Return the lower triangle

Returns the lower triangular part of submatrix A(imin:imax,jmin:jmax), optionally rescaling row/col indices to the range 1:imax-imin+1,1:jmax-jmin+1 and returing the complementary upper triangle.

Type: Asynchronous.

On Entry

a the sparse matrix.

A variable of type psb_Tspmat_type. Scope: local.

diag Include diagonals up to this one; diag=1 means the first superdiagonal,
 diag=-1 means the first subdiagonal. Default 0.

imin,imax,jmin,jmax Minimum and maximum row and column indices. Type: optional.

rscale,cscale Whether to rescale row/column indices. Type: optional.

On Return

1 A copy of the lower triangle of a.

A variable of type psb_Tspmat_type.

u (optional) A copy of the upper triangle of a. A variable of type psb_Tspmat_type.

info Return code.

```
triu — Return the upper triangle
```

Returns the upper triangular part of submatrix A(imin:imax,jmin:jmax), optionally rescaling row/col indices to the range 1:imax-imin+1,1:jmax-jmin+1, and returing the complementary lower triangle.

Type: Asynchronous.

On Entry

a the sparse matrix.

A variable of type psb_Tspmat_type.

Scope: local.

 $\begin{tabular}{ll} \bf diag Include \ diagonals \ up \ to \ this \ one; \ \tt diag=1 \ means \ the \ first \ superdiagonal, \\ \bf diag=-1 \ means \ the \ first \ subdiagonal. \ Default \ 0. \end{tabular}$

imin,imax,jmin,jmax Minimum and maximum row and column indices. Type: optional.

rscale,cscale Whether to rescale row/column indices. Type: optional.

On Return

u A copy of the upper triangle of a.A variable of type psb_Tspmat_type.

l (optional) A copy of the lower triangle of a.
A variable of type psb_Tspmat_type.

info Return code.

$psb_set_mat_default$ — Set default storage format

```
call psb_set_mat_default(a)
```

Type: Asynchronous.

On Entry

a a variable of class(psb_T_base_sparse_mat) requesting a new default storage format.Type: required.

clone — Clone current object

call a%clone(b,info)

Type: Asynchronous.

a the sparse matrix. Scope: **local**.

On Return

b A copy of the input object.

info Return code.

3.2.2 Named Constants

psb_dupl_ovwrt_ Duplicate coefficients should be overwritten (i.e. ignore duplications)

psb_dupl_add_ Duplicate coefficients should be added;

psb_dupl_err_ Duplicate coefficients should trigger an error conditino

psb_upd_dflt_ Default update strategy for matrix coefficients;

psb_upd_srch_ Update strategy based on search into the data structure;

psb_upd_perm_ Update strategy based on additional permutation data (see tools routine description).

3.3 Dense Vector Data Structure

The psb_T_vect_type data structure encapsulates the dense vectors in a way similar to sparse matrices, i.e. including a base type psb_T_base_vect_type. The user will not, in general, access the vector components directly, but rather via the routines of sec. 6. Among other simple things, we define here an extraction method that can be used to get a full copy of the part of the vector stored on the local process.

The type declaration is shown in figure 5 where \mathtt{T} is a placeholder for the data type and precision variants

- I Integer;
- S Single precision real;
- **D** Double precision real;
- C Single precision complex;
- **Z** Double precision complex.

The actual data is contained in the polymorphic component v%v; the separation between the application and the actual data is essential for cases where it is necessary to link to data storage made available elsewhere outside the direct control of the compiler/application, e.g. data stored in a graphics accelerator's private memory.

```
type psb_T_base_vect_type
  TYPE(KIND_), allocatable :: v(:)
end type psb_T_base_vect_type

type psb_T_vect_type
  class(psb_T_base_vect_type), allocatable :: v
end type psb_T_vect_type
```

Figure 5: The PSBLAS defined data type that contains a dense vector.

3.3.1 Vector Methods

On Return

Function value The number of rows of dense vector v.

```
sizeof — Get memory occupation in bytes of a dense vector
memory_size = v%sizeof()
```

Type: Asynchronous.

On Entry

```
v the dense vector
Scope: local
```

On Return

Function value The memory occupation in bytes.

```
set — Set contents of the vector
call  v%set(alpha[,first,last])
call  v%set(vect[,first,last])
call  v%zero()
Type: Asynchronous.
On Entry
```

```
v the dense vector
Scope: local
```

alpha A scalar value.

Scope: local
Type: required
Intent: in.

Specified as: a number of the data type indicated in Table 1.

first, last Boundaries for setting in the vector.

Scope: local Type: optional Intent: in.

Specified as: integers.

vect An array

Scope: local Type: required Intent: in.

Specified as: a number of the data type indicated in Table 1.

Note that a call to v%zero() is provided as a shorthand, but is equivalent to a call to v%set(zero) with the zero constant having the appropriate type and kind.

On Return

 ${f v}$ the dense vector, with updated entries Scope: local

get_vect — Get a copy of the vector contents

extv = v%get_vect()

Type: Asynchronous.

On Entry

v the dense vector Scope: local

On Return

Function value An allocatable array holding a copy of the dense vector contents.

```
clone — Clone current object
call x%clone(y,info)
Type: Asynchronous.
On Entry
x the dense vector.
```

On Return

y A copy of the input object.

Scope: local.

info Return code.

3.4 Preconditioner data structure

Our base library offers support for simple well known preconditioners like Diagonal Scaling or Block Jacobi with incomplete factorization ILU(0).

A preconditioner is held in the psb_prec_type data structure reported in figure 6. The psb_prec_type data type may contain a simple preconditioning matrix with the associated communication descriptor. The internal preconditioner is allocated appropriately with the dynamic type corresponding to the desired preconditioner.

```
type psb_Tprec_type
  class(psb_T_base_prec_type), allocatable :: prec
end type psb_Tprec_type
```

Figure 6: The PSBLAS defined data type that contains a preconditioner.

3.5 Heap data structure

Among the tools routines of sec. 6, we have a number of sorting utilities; the heap sort is implemented in terms of heaps having the following signatures:

psb_T_heap : a heap containing elements of type T, where T can be i,s,c,d,z
for integer, real and complex data;

 ${\tt psb_T_idx_heap}$: a heap containing elements of type T, as above, together with an integer index.

Given a heap object, the following methods are defined on it:

init Initialize memory; also choose ascending or descending order;

howmany Current heap occupancy;

insert Add an item (or an item and its index);

 $\mathbf{get_first}$ Remove and return the first element;

dump Print on file;

free Release memory.

These objects are used in MLD2P4 to implement the factorization algorithms.

4 Computational routines

psb_geaxpby — General Dense Matrix Sum

This subroutine is an interface to the computational kernel for dense matrix sum:

$$y \leftarrow \alpha \ x + \beta y$$

call psb_geaxpby(alpha, x, beta, y, desc_a, info)

x, y, α, β	Subroutine
Short Precision Real	$psb_geaxpby$
Long Precision Real	$psb_geaxpby$
Short Precision Complex	$psb_geaxpby$
Long Precision Complex	$psb_geaxpby$

Table 1: Data types

Type: Synchronous.

On Entry

alpha the scalar α .

Scope: **global**Type: **required**Intent: **in**.

Specified as: a number of the data type indicated in Table 1.

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 1. The rank of x must be the same of y.

beta the scalar β .

Scope: **global**Type: **required**Intent: **in**.

Specified as: a number of the data type indicated in Table 1.

 \mathbf{y} the local portion of the global dense matrix y.

Scope: local Type: required Intent: inout.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of the type indicated in Table 1. The rank of y must be the same of x.

desc_a contains data structures for communications.

Scope: local

Type: $\mathbf{required}$ Intent: \mathbf{in} .

Specified as: an object of type psb_desc_type .

On Return

 \mathbf{y} the local portion of result submatrix y.

Scope: local Type: required Intent: inout.

Specified as: a rank one or two array or an object of type psb_T_vect_type

containing numbers of the type indicated in Table 1.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

psb_gedot — Dot Product

This function computes dot product between two vectors x and y. If x and y are real vectors it computes dot-product as:

$$dot \leftarrow x^T y$$

Else if x and y are complex vectors then it computes dot-product as:

$$dot \leftarrow x^H y$$

psb_gedot(x, y, desc_a, info)

dot, x, y	Function
Short Precision Real	psb_gedot
Long Precision Real	psb_gedot
Short Precision Complex	psb_gedot
Long Precision Complex	psb_gedot

Table 2: Data types

Type: Synchronous.

On Entry

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 2. The rank of x must be the same of y.

 \mathbf{y} the local portion of global dense matrix y.

Scope: **local**Type: **required**Intent: **in**.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 2. The rank of y must be the same of x.

 $\mathbf{desc_a}$ contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_desc_type.

On Return

Function value is the dot product of subvectors x and y.

Scope: global

Specified as: a number of the data type indicated in Table 2.

 $\mathbf{info} \ \, \mathrm{Error} \,\, \mathrm{code}.$

Scope: local Type: required Intent: out.

psb_gedots — Generalized Dot Product

This subroutine computes a series of dot products among the columns of two dense matrices x and y:

 $res(i) \leftarrow x(:,i)^T y(:,i)$

If the matrices are complex, then the usual convention applies, i.e. the conjugate transpose of x is used. If x and y are of rank one, then res is a scalar, else it is a rank one array.

call psb_gedots(res, x, y, desc_a, info)

res, x, y	Subroutine
Short Precision Real	psb_gedots
Long Precision Real	psb_gedots
Short Precision Complex	psb_gedots
Long Precision Complex	psb_gedots

Table 3: Data types

Type: Synchronous.

On Entry

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 3. The rank of x must be the same of y.

 \mathbf{y} the local portion of global dense matrix y.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 3. The rank of y must be the same of x.

desc_a contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_desc_type.

On Return

res is the dot product of subvectors x and y.

Scope: **global** Intent: **out**.

Specified as: a number or a rank-one array of the data type indicated in Table 2.

 $\mathbf{info} \ \, \mathrm{Error} \,\, \mathrm{code}.$

Scope: local Type: required Intent: out.

psb_normi — Infinity-Norm of Vector

This function computes the infinity-norm of a vector x. If x is a real vector it computes infinity norm as:

$$amax \leftarrow \max_{i} |x_i|$$

else if x is a complex vector then it computes the infinity-norm as:

$$amax \leftarrow \max_{i} \left(|re(x_i)| + |im(x_i)| \right)$$

psb_geamax(x, desc_a, info)
psb_normi(x, desc_a, info)

\overline{amax}	\overline{x}	Function
Short Precision Real	Short Precision Real	psb_geamax
Long Precision Real	Long Precision Real	psb_geamax
Short Precision Real	Short Precision Complex	psb_geamax
Long Precision Real	Long Precision Complex	psb_geamax

Table 4: Data types

Type: Synchronous.

On Entry

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type psb_T_vect_type

containing numbers of type specified in Table 4.

 ${f desc_a}$ contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: an object of type ${\tt psb_desc_type}.$

On Return

Function value is the infinity norm of subvector x.

Scope: global

Specified as: a long precision real number.

info Error code.

Scope: local
Type: required
Intent: out.

psb_geamaxs — Generalized Infinity Norm

This subroutine computes a series of infinity norms on the columns of a dense matrix x:

$$res(i) \leftarrow \max_{k} |x(k,i)|$$

call psb_geamaxs(res, x, desc_a, info)

res	x	Subroutine
Short Precision Real	Short Precision Real	$psb_geamaxs$
Long Precision Real	Long Precision Real	$psb_geamaxs$
Short Precision Real	Short Precision Complex	$psb_geamaxs$
Long Precision Real	Long Precision Complex	$psb_geamaxs$

Table 5: Data types

Type: Synchronous.

On Entry

 ${f x}$ the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type psb_T_vect_type containing numbers of type specified in Table 5.

desc_a contains data structures for communications.

Scope: **local**Type: **required**Intent: **in**.

Specified as: an object of type psb_desc_type.

On Return

res is the infinity norm of the columns of x.

Scope: **global** Intent: **out**.

Specified as: a number or a rank-one array of long precision real numbers.

info Error code.

Scope: local Type: required Intent: out.

psb_norm1 — 1-Norm of Vector

This function computes the 1-norm of a vector x. If x is a real vector it computes 1-norm as:

$$asum \leftarrow ||x_i||$$

else if x is a complex vector then it computes 1-norm as:

$$asum \leftarrow ||re(x)||_1 + ||im(x)||_1$$

psb_geasum(x, desc_a, info)
psb_norm1(x, desc_a, info)

asum	x	Function
Short Precision Real	Short Precision Real	psb_geasum
Long Precision Real	Long Precision Real	psb_geasum
Short Precision Real	Short Precision Complex	psb_geasum
Long Precision Real	Long Precision Complex	psb_geasum

Table 6: Data types

Type: Synchronous.

On Entry

 \mathbf{x} the local portion of global dense matrix x.

Scope: **local**Type: **required**Intent: **in**.

Specified as: a rank one or two array or an object of type psb_T_vect_type

containing numbers of type specified in Table 6.

desc_a contains data structures for communications.

Scope: **local**Type: **required**Intent: **in**.

Specified as: an object of type psb_desc_type.

On Return

Function value is the 1-norm of vector x.

Scope: global

Specified as: a long precision real number.

info Error code.

Scope: local
Type: required
Intent: out.

psb_geasums — Generalized 1-Norm of Vector

This subroutine computes a series of 1-norms on the columns of a dense matrix x:

$$res(i) \leftarrow \max_{k} |x(k,i)|$$

This function computes the 1-norm of a vector x. If x is a real vector it computes 1-norm as:

$$res(i) \leftarrow \|x_i\|$$

else if x is a complex vector then it computes 1-norm as:

$$res(i) \leftarrow ||re(x)||_1 + ||im(x)||_1$$

call psb_geasums(res, x, desc_a, info)

res	x	Subroutine
Short Precision Real	Short Precision Real	$psb_geasums$
Long Precision Real	Long Precision Real	$psb_geasums$
Short Precision Real	Short Precision Complex	$psb_geasums$
Long Precision Real	Long Precision Complex	$psb_geasums$

Table 7: Data types

Type: Synchronous.

On Entry

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type psb_T_vect_type containing numbers of type specified in Table 7.

 $\mathbf{desc_a}$ contains data structures for communications.

Scope: **local**Type: **required**Intent: **in**.

Specified as: an object of type psb_desc_type.

On Return

res contains the 1-norm of (the columns of) x.

Scope: **global** Intent: **out**.

Short as: a long precision real number. Specified as: a long precision real number.

info Error code.

Scope: local Type: required Intent: out.

psb_norm2 — 2-Norm of Vector

This function computes the 2-norm of a vector x. If x is a real vector it computes 2-norm as:

$$nrm2 \leftarrow \sqrt{x^T x}$$

else if x is a complex vector then it computes 2-norm as:

$$nrm2 \leftarrow \sqrt{x^Hx}$$

nrm2	x	Function
Short Precision Real	Short Precision Real	psb_genrm2
Long Precision Real	Long Precision Real	psb_genrm2
Short Precision Real	Short Precision Complex	psb_genrm2
Long Precision Real	Long Precision Complex	psb_genrm2

Table 8: Data types

psb_genrm2(x, desc_a, info)
psb_norm2(x, desc_a, info)

Type: Synchronous.

On Entry

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type psb_T_vect_type

containing numbers of type specified in Table 8.

 $\mathbf{desc_a}$ contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_desc_type.

On Return

Function Value is the 2-norm of subvector x.

Scope: **global**Type: **required**

Specified as: a long precision real number.

info Error code.

Scope: local
Type: required
Intent: out.

psb_genrm2s — Generalized 2-Norm of Vector

This subroutine computes a series of 2-norms on the columns of a dense matrix x:

$$res(i) \leftarrow ||x(:,i)||_2$$

call psb_genrm2s(res, x, desc_a, info)

res	x	Subroutine
Short Precision Real	Short Precision Real	psb_genrm2s
Long Precision Real	Long Precision Real	$psb_genrm2s$
Short Precision Real	Short Precision Complex	$psb_genrm2s$
Long Precision Real	Long Precision Complex	$psb_genrm2s$

Table 9: Data types

Type: Synchronous.

On Entry

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type psb_T_vect_type containing numbers of type specified in Table 9.

 $\mathbf{desc_a}$ contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_desc_type.

On Return

res contains the 1-norm of (the columns of) x.

Scope: **global** Intent: **out**.

Specified as: a long precision real number.

info Error code.

Scope: local
Type: required
Intent: out.

psb_norm1 — 1-Norm of Sparse Matrix

This function computes the 1-norm of a matrix A:

 $nrm1 \leftarrow ||A||_1$

where:

A represents the global matrix A

A	Function
Short Precision Real	psb_spnrm1
Long Precision Real	psb_spnrm1
Short Precision Complex	psb_spnrm1
Long Precision Complex	psb_spnrm1

Table 10: Data types

psb_spnrm1(A, desc_a, info)
psb_norm1(A, desc_a, info)

Type: Synchronous.

On Entry

 \mathbf{a} the local portion of the global sparse matrix A.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_Tspmat_type.

 $\mathbf{desc_a}$ contains data structures for communications.

Scope: **local**Type: **required**Intent: **in**.

Specified as: an object of type psb_desc_type.

On Return

Function value is the 1-norm of sparse submatrix A.

Scope: **global**

Specified as: a long precision real number.

info Error code.

Scope: local Type: required Intent: out.

psb_normi — Infinity Norm of Sparse Matrix

This function computes the infinity-norm of a matrix A:

 $nrmi \leftarrow ||A||_{\infty}$

where:

A represents the global matrix A

A	Function
Short Precision Real	psb_spnrmi
Long Precision Real	psb_spnrmi
Short Precision Complex	psb_spnrmi
Long Precision Complex	psb_spnrmi

Table 11: Data types

psb_spnrmi(A, desc_a, info)
psb_normi(A, desc_a, info)

Type: Synchronous.

On Entry

 \mathbf{a} the local portion of the global sparse matrix A.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_Tspmat_type.

 $\mathbf{desc_a}$ contains data structures for communications.

Scope: local Type: required Intent: in.

Specified as: an object of type psb_desc_type.

On Return

Function value is the infinity-norm of sparse submatrix A.

Scope: global

Specified as: a long precision real number.

info Error code.

Scope: local
Type: required
Intent: out.

psb_spmm — Sparse Matrix by Dense Matrix Product

This subroutine computes the Sparse Matrix by Dense Matrix Product:

$$y \leftarrow \alpha A x + \beta y \tag{1}$$

$$y \leftarrow \alpha A^T x + \beta y \tag{2}$$

$$y \leftarrow \alpha A^H x + \beta y \tag{3}$$

where:

x is the global dense matrix $x_{:::}$

y is the global dense matrix $y_{:,:}$

A is the global sparse matrix A

A, x, y, α, β	Subroutine
Short Precision Real	psb_spmm
Long Precision Real	psb_spmm
Short Precision Complex	psb_spmm
Long Precision Complex	psb_spmm

Table 12: Data types

Type: Synchronous.

On Entry

alpha the scalar α .

Scope: **global**Type: **required**Intent: **in**.

Specified as: a number of the data type indicated in Table 12.

 \mathbf{a} the local portion of the sparse matrix A.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_Tspmat_type.

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 12. The rank of x must be the same of y.

```
beta the scalar \beta.
     Scope: global
     Type: required
     Intent: in.
     Specified as: a number of the data type indicated in Table 12.
\mathbf{y} the local portion of global dense matrix y.
     Scope: local
     Type: required
     Intent: inout.
     Specified as: a rank one or two array or an object of type psb_T_vect_type
     containing numbers of type specified in Table 12. The rank of y must be
     the same of x.
desc_a contains data structures for communications.
     Scope: local
     Type: required
     Intent: in.
     Specified as: an object of type psb_desc_type.
trans indicates what kind of operation to perform.
     trans = N the operation is specified by equation 1
     trans = T the operation is specified by equation 2
     trans = C the operation is specified by equation 3
     Scope: global
     Type: optional
     Intent: in.
     Default: trans = N
     Specified as: a character variable.
work work array.
     Scope: local
     Type: optional
     Intent: inout.
     Specified as: a rank one array of the same type of x and y with the
     TARGET attribute.
On Return
\mathbf{y} the local portion of result matrix y.
     Scope: local
     Type: required
```

Intent: inout.

Specified as: an array of rank one or two containing numbers of type specified in Table 12.

info Error code.

Scope: local Type: required Intent: out.

psb_spsm — Triangular System Solve

This subroutine computes the Triangular System Solve:

$$y \leftarrow \alpha T^{-1}x + \beta y$$

$$y \leftarrow \alpha DT^{-1}x + \beta y$$

$$y \leftarrow \alpha T^{-1}Dx + \beta y$$

$$y \leftarrow \alpha T^{-T}x + \beta y$$

$$y \leftarrow \alpha DT^{-T}x + \beta y$$

$$y \leftarrow \alpha T^{-T}Dx + \beta y$$

$$y \leftarrow \alpha T^{-T}Dx + \beta y$$

$$y \leftarrow \alpha T^{-H}x + \beta y$$

$$y \leftarrow \alpha DT^{-H}x + \beta y$$

$$y \leftarrow \alpha T^{-H}Dx + \beta y$$

where:

x is the global dense matrix $x_{:,:}$

y is the global dense matrix $y_{:,:}$

 ${\cal T}\,$ is the global sparse block triangular submatrix ${\cal T}\,$

D is the scaling diagonal matrix.

$T, x, y, D, \alpha, \beta$	Subroutine
Short Precision Real	psb_spsm
Long Precision Real	psb_spsm
Short Precision Complex	psb_spsm
Long Precision Complex	psb_spsm

Table 13: Data types

Type: Synchronous.

On Entry

alpha the scalar α .

Scope: **global**Type: **required**Intent: **in**.

Specified as: a number of the data type indicated in Table 13.

```
{f t} the global portion of the sparse matrix T.
```

Scope: local
Type: required
Intent: in.

Specified as: an object type specified in § 3.

 \mathbf{x} the local portion of global dense matrix x.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 13. The rank of x must be the same of y.

one same or g

beta the scalar β . Scope: global Type: required Intent: in.

Specified as: a number of the data type indicated in Table 13.

 \mathbf{y} the local portion of global dense matrix y.

Scope: local
Type: required
Intent: inout.

Specified as: a rank one or two array or an object of type $psb_T_vect_type$ containing numbers of type specified in Table 13. The rank of y must be the same of x.

desc_a contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: an object of type psb_desc_type.

trans specify with *unitd* the operation to perform.

trans = 'N' the operation is with no transposed matrix

trans = T' the operation is with transposed matrix.

trans = 'C' the operation is with conjugate transposed matrix.

Scope: **global**Type: **optional**Intent: **in**.

Default: trans = N

Specified as: a character variable.

unitd specify with *trans* the operation to perform.

unitd = 'U' the operation is with no scalingunitd = 'L' the operation is with left scaling

unitd = 'R' the operation is with right scaling.

```
Scope: global
Type: optional
Intent: in.
```

Default: unitd = U

Specified as: a character variable.

choice specifies the update of overlap elements to be performed on exit:

```
psb_none_
psb_sum_
psb_avg_
psb_square_root_
Scope: global
Type: optional
Intent: in.
```

Default: psb_avg_

Specified as: an integer variable.

diag the diagonal scaling matrix.

Scope: local Type: optional Intent: in.

Default: diag(1) = 1(noscaling)

Specified as: a rank one array containing numbers of the type indicated

in Table 13.

work a work array.

Scope: local Type: optional Intent: inout.

Specified as: a rank one array of the same type of x with the TARGET

attribute.

On Return

 \mathbf{y} the local portion of global dense matrix y.

Scope: local Type: required Intent: inout.

Specified as: an array of rank one or two containing numbers of type

specified in Table 13.

info Error code.

Scope: local Type: required Intent: out.

5 Communication routines

The routines in this chapter implement various global communication operators on vectors associated with a discretization mesh. For auxiliary communication routines not tied to a discretization space see 6.

psb_halo — Halo Data Communication

These subroutines gathers the values of the halo elements:

 $x \leftarrow x$

where:

x is a global dense submatrix.

α, x	Subroutine
Integer	psb_halo
Short Precision Real	psb_halo
Long Precision Real	psb_halo
Short Precision Complex	psb_halo
Long Precision Complex	psb_halo

Table 14: Data types

```
call psb_halo(x, desc_a, info)
call psb_halo(x, desc_a, info, work, data)
```

Type: Synchronous.

On Entry

 \mathbf{x} global dense matrix x.

Scope: local
Type: required
Intent: inout.

Specified as: a rank one or two array or an object of type psb_T_vect_type

containing numbers of type specified in Table 14.

desc_a contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: a structured data of type psb_desc_type.

work the work array.

Scope: local Type: optional Intent: inout.

Specified as: a rank one array of the same type of x.

data index list selector.

Scope: **global**Type: **optional**

Specified as: an integer. Values:psb_comm_halo_,psb_comm_mov_, psb_comm_ext_,

default: psb_comm_halo_. Chooses the index list on which to base the

data exchange.

On Return

 \mathbf{x} global dense result matrix x.

Scope: local
Type: required
Intent: inout.

Returned as: a rank one or two array containing numbers of type specified

in Table 14.

info the local portion of result submatrix y.

Scope: local
Type: required
Intent: out.

An integer value that contains an error code.




Figure 7: Sample discretization mesh.

Usage Example Consider the discretization mesh depicted in fig. 7, partitioned among two processes as shown by the dashed line; the data distribution is such that each process will own 32 entries in the index space, with a halo made of 8 entries placed at local indices 33 through 40. If process 0 assigns an initial value of 1 to its entries in the x vector, and process 1 assigns a value of 2, then after a call to psb_halo the contents of the local vectors will be the following:

I GLOB(I) X(I) I GLOB(I) X(I) 1 1 1.0 1 33 2.0 2 2 1.0 2 34 2.0 3 3 1.0 3 35 2.0 4 4 1.0 4 36 2.0 5 5 1.0 5 37 2.0 6 6 1.0 6 38 2.0 7 7 1.0 7 39 2.0 8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 15 15 17 2.0 <th></th> <th>Proces</th> <th>ss 0</th> <th></th> <th>Process</th> <th>1</th>		Proces	ss 0		Process	1
2 2 1.0 2 34 2.0 3 3 1.0 3 35 2.0 4 4 1.0 4 36 2.0 5 5 1.0 5 37 2.0 6 6 1.0 6 38 2.0 7 7 1.0 7 39 2.0 8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15	I	GLOB(I)	X(I)	I	GLOB(I)	X(I)
3 3 1.0 3 35 2.0 4 4 1.0 4 36 2.0 5 5 1.0 5 37 2.0 6 6 1.0 6 38 2.0 7 7 1.0 7 39 2.0 8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 11 11 1.0 11 43 2.0 11 11 1.0 11 43 2.0 11 11 1.0 11 43 2.0 11 11 1.0 11 43 2.0 11 14 4.0 14 4.6 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0	1		1.0	1	33	2.0
4 4 1.0 4 36 2.0 5 5 1.0 5 37 2.0 6 6 1.0 6 38 2.0 7 7 1.0 7 39 2.0 8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 20 20 1.0 20 52 2.0 <td>2</td> <td></td> <td>1.0</td> <td>2</td> <td>34</td> <td>2.0</td>	2		1.0	2	34	2.0
5 5 1.0 5 37 2.0 6 6 1.0 6 38 2.0 7 7 1.0 7 39 2.0 8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18<	3	3	1.0	3	35	2.0
6 6 1.0 6 38 2.0 7 7 1.0 7 39 2.0 8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2	4	4	1.0	4	36	2.0
7 7 1.0 7 39 2.0 8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 <t< td=""><td>5</td><td></td><td>1.0</td><td>5</td><td>37</td><td>2.0</td></t<>	5		1.0	5	37	2.0
8 8 1.0 8 40 2.0 9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55	6		1.0	6	38	2.0
9 9 1.0 9 41 2.0 10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56			1.0	7	39	
10 10 1.0 10 42 2.0 11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57	8		1.0	8	40	
11 11 1.0 11 43 2.0 12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58	9	9	1.0	9	41	2.0
12 12 1.0 12 44 2.0 13 13 1.0 13 45 2.0 14 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27	10	10	1.0	10	42	2.0
13 13 1.0 13 45 2.0 14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60	11	11	1.0	11	43	2.0
14 14 1.0 14 46 2.0 15 15 1.0 15 47 2.0 16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 30 30 1.0 30 62	12	12	1.0	12	44	2.0
15 15 1.0 15 47 2.0 16 16 16 18 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0	13	13	1.0	13	45	2.0
16 16 1.0 16 48 2.0 17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64	14	14	1.0	14	46	2.0
17 17 1.0 17 49 2.0 18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25	15	15	1.0	15	47	2.0
18 18 1.0 18 50 2.0 19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25	16	16	1.0	16	48	2.0
19 19 1.0 19 51 2.0 20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26	17	17	1.0	17	49	2.0
20 20 1.0 20 52 2.0 21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27	18	18	1.0	18	50	2.0
21 21 1.0 21 53 2.0 22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28		19	1.0	19	51	2.0
22 22 1.0 22 54 2.0 23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	20	20	1.0	20	52	2.0
23 23 1.0 23 55 2.0 24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 <tr< td=""><td>21</td><td>21</td><td>1.0</td><td>21</td><td>53</td><td>2.0</td></tr<>	21	21	1.0	21	53	2.0
24 24 1.0 24 56 2.0 25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31	22	22	1.0	22	54	2.0
25 25 1.0 25 57 2.0 26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	23	23	1.0	23	55	2.0
26 26 1.0 26 58 2.0 27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	24	24	1.0	24	56	2.0
27 27 1.0 27 59 2.0 28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	25	25	1.0	25	57	2.0
28 28 1.0 28 60 2.0 29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	26	26	1.0	26	58	2.0
29 29 1.0 29 61 2.0 30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	27	27	1.0	27	59	2.0
30 30 1.0 30 62 2.0 31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	28	28	1.0	28	60	2.0
31 31 1.0 31 63 2.0 32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	29	29	1.0	29	61	2.0
32 32 1.0 32 64 2.0 33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	30	30	1.0	30	62	2.0
33 33 2.0 33 25 1.0 34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0			1.0		63	
34 34 2.0 34 26 1.0 35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0			1.0		64	2.0
35 35 2.0 35 27 1.0 36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0		33	2.0		25	
36 36 2.0 36 28 1.0 37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0		34	2.0		26	1.0
37 37 2.0 37 29 1.0 38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0	35	35	2.0	35	27	1.0
38 38 2.0 38 30 1.0 39 39 2.0 39 31 1.0						
39 39 2.0 39 31 1.0						1.0
		38	2.0	38	30	1.0
40 40 2.0 40 32 1.0	39	39	2.0	39	31	1.0
	40	40	2.0	40	32	1.0

psb_ovrl — Overlap Update

These subroutines applies an overlap operator to the input vector:

$$x \leftarrow Qx$$

where:

x is the global dense submatrix x

Q is the overlap operator; it is the composition of two operators P_a and P^T .

\overline{x}	Subroutine
Short Precision Real	psb_ovrl
Long Precision Real	psb_ovrl
Short Precision Complex	psb_ovrl
Long Precision Complex	psb_ovrl

Table 15: Data types

```
call psb_ovrl(x, desc_a, info)
call psb_ovrl(x, desc_a, info, update=update_type, work=work)
```

Type: Synchronous.

On Entry

 \mathbf{x} global dense matrix x.

Scope: local
Type: required
Intent: inout.

Specified as: a rank one or two array or an object of type psb_T_vect_type containing numbers of type specified in Table 15.

 $\mathbf{desc_a}$ contains data structures for communications.

Scope: **local** Type: **required** Intent: **in**.

Specified as: a structured data of type psb_desc_type .

update Update operator.

```
update = psb_none_ Do nothing;

update = psb_add_ Sum overlap entries, i.e. apply P^T;

update = psb_avg_ Average overlap entries, i.e. apply P_aP^T;
```

Scope: **global** Intent: **in**.

Default: $update_type = psb_avg_$

Scope: global

Specified as: a integer variable.

work the work array.

Scope: **local**Type: **optional**Intent: **inout**.

Specified as: a one dimensional array of the same type of x.

On Return

 \mathbf{x} global dense result matrix x.

Scope: local Type: required Intent: inout.

Specified as: an array of rank one or two containing numbers of type

specified in Table 15.

info Error code.

Scope: **local**Type: **required**Intent: **out**.

An integer value; 0 means no error has been detected.

Notes

- 1. If there is no overlap in the data distribution associated with the descriptor, no operations are performed;
- 2. The operator P^T performs the reduction sum of overlap elements; it is a "prolongation" operator P^T that replicates overlap elements, accounting for the physical replication of data;
- 3. The operator P_a performs a scaling on the overlap elements by the amount of replication; thus, when combined with the reduction operator, it implements the average of replicated elements over all of their instances.

Example of use Consider the discretization mesh depicted in fig. 8, partitioned among two processes as shown by the dashed lines, with an overlap of 1 extra layer with respect to the partition of fig. 7; the data distribution is such that each process will own 40 entries in the index space, with an overlap of 16 entries placed at local indices 25 through 40; the halo will run from local index 41 through local index 48.. If process 0 assigns an initial value of 1 to its entries in the x vector, and process 1 assigns a value of 2, then after a call to psb_ovrl with psb_avg_ and a call to psb_halo_ the contents of the local vectors will be the following (showing a transition among the two subdomains)

	Proce	ess 0		Process 1	L
I	GLOB(I)	X(I)	I	GLOB(I)	X(I)
1	ĺ	1.0	1	33	1.5
2	2	1.0	2	34	1.5
3	3	1.0	3	35	1.5
4	4	1.0	4	36	1.5
5	5	1.0	5	37	1.5
6	6	1.0	6	38	1.5
7	7	1.0	7	39	1.5
8	8	1.0	8	40	1.5
9	9	1.0	9	41	2.0
10	10	1.0	10	42	2.0
11	11	1.0	11	43	2.0
12	12	1.0	12	44	2.0
13	13	1.0	13	45	2.0
14	14	1.0	14	46	2.0
15	15	1.0	15	47	2.0
16	16	1.0	16	48	2.0
17	17	1.0	17	49	2.0
18	18	1.0	18	50	2.0
19	19	1.0	19	51	2.0
20	20	1.0	20	52	2.0
21	21	1.0	21	53	2.0
22	22	1.0	22	54	2.0
23	23	1.0	23	55	2.0
24	24	1.0	24	56	2.0
25	25	1.5	25	57	2.0
26	26	1.5	26	58	2.0
27	27	1.5	27	59	2.0
28	28	1.5	28	60	2.0
29	29	1.5	29	61	2.0
30	30	1.5	30	62	2.0
31	31	1.5	31	63	2.0
32	32	1.5	32	64	2.0
33	33	1.5	33	25	1.5
34	34	1.5	34	26	1.5
35	35	1.5	35	27	1.5
36	36	1.5	36	28	1.5
37	37	1.5	37	29	1.5
38	38	1.5	38	30	1.5
39	39	1.5	39	31	1.5
40	40	1.5	40	32	1.5
41	41	2.0	41	17	1.0
42	42	2.0	42	18	1.0
43	43	2.0	43	19	1.0
44	44	2.0	44	20	1.0
45	45	2.0	45	21	1.0
46	46	2.0	46	22	1.0
47	47	2.0	47	23	1.0
48	48	2.0	48	24	1.0




Figure 8: Sample discretization mesh.

psb_gather — Gather Global Dense Matrix

These subroutines collect the portions of global dense matrix distributed over all process into one single array stored on one process.

$$glob_x \leftarrow collect(loc_x_i)$$

where:

 $glob_x$ is the global submatrix $glob_x_{1:m,1:n}$

 loc_x_i is the local portion of global dense matrix on process i.

collect is the collect function.

x_i, y	Subroutine
Integer	psb_gather
Short Precision Real	psb_gather
Long Precision Real	psb_gather
Short Precision Complex	psb_gather
Long Precision Complex	psb_gather

Table 16: Data types

```
call psb_gather(glob_x, loc_x, desc_a, info, root)
call psb_gather(glob_x, loc_x, desc_a, info, root)
```

Type: Synchronous.

On Entry

 $\mathbf{loc}_{-}\mathbf{x}$ the local portion of global dense matrix $glob_{-}x$.

Scope: local
Type: required
Intent: in.

Specified as: a rank one or two array or an object of type psb_T_vect_type

indicated in Table 16.

desc_a contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: a structured data of type psb_desc_type.

root The process that holds the global copy. If root = -1 all the processes will

have a copy of the global vector.

Scope: **global**Type: **optional**Intent: **in**.

Specified as: an integer variable $-1 \le root \le np - 1$, default -1.

On Return

 $\mathbf{glob}_{\boldsymbol{-}}\mathbf{x}$ The array where the local parts must be gathered.

Scope: **global**Type: **required**Intent: **out**.

Specified as: a rank one or two array with the ${\tt ALLOCATABLE}$ attribute.

info Error code.

Scope: local
Type: required
Intent: out.

psb_scatter — Scatter Global Dense Matrix

These subroutines scatters the portions of global dense matrix owned by a process to all the processes in the processes grid.

 $loc_x_i \leftarrow scatter(glob_x)$

where:

 $glob_x$ is the global matrix $glob_x_{1:m,1:n}$

 loc_x_i is the local portion of global dense matrix on process i.

scatter is the scatter function.

x_i, y	Subroutine
Integer	$psb_scatter$
Short Precision Real	$psb_scatter$
Long Precision Real	$psb_scatter$
Short Precision Complex	$psb_scatter$
Long Precision Complex	$psb_scatter$

Table 17: Data types

call psb_scatter(glob_x, loc_x, desc_a, info, root, mold)

Type: Synchronous.

On Entry

glob_x The array that must be scattered into local pieces.

Scope: **global**Type: **required**Intent: **in**.

Specified as: a rank one or two array.

 $\mathbf{desc}_{-\mathbf{a}}$ contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: a structured data of type psb_desc_type.

root The process that holds the global copy. If root = -1 all the processes

have a copy of the global vector.

Scope: **global**Type: **optional**Intent: **in**.

Specified as: an integer variable $-1 \le root \le np - 1$, default psb_root_,

i.e. process 0.

mold The desired dynamic type for the internal vector storage.

Scope: local.
Type: optional.
Intent: in.

Specified as: an object of a class derived from psb_T_base_vect_type; this

is only allowed when loc_x is of type psb_T_vect_type.

On Return

 loc_x the local portion of global dense matrix $glob_x$.

Scope: local
Type: required
Intent: out.

Specified as: a rank one or two ALLOCATABLE array or an object of type psb_T_vect_type containing numbers of the type indicated in Table 17.

info Error code.

Scope: local
Type: required
Intent: out.

6 Data management routines

psb_cdall — Allocates a communication descriptor

```
call psb_cdall(icontxt, desc_a, info,mg=mg,parts=parts)
call psb_cdall(icontxt, desc_a, info,vg=vg,[mg=mg,flag=flag])
call psb_cdall(icontxt, desc_a, info,vl=vl,[nl=nl,globalcheck=.true.,lidx=lidx])
call psb_cdall(icontxt, desc_a, info,nl=nl)
call psb_cdall(icontxt, desc_a, info,mg=mg,repl=.true.)
```

This subroutine initializes the communication descriptor associated with an index space. One of the optional arguments parts, vg, vl, nl or repl must be specified, thereby choosing the specific initialization strategy.

On Entry

```
Type: Synchronous.
```

icontxt the communication context.

Scope:global.

Type:required.

Intent: in.

Specified as: an integer value.

vg Data allocation: each index $i \in \{1 \dots mg\}$ is allocated to process vg(i).

Scope:global.

Type:optional.

Intent: in.

Specified as: an integer array.

flag Specifies whether entries in vg are zero- or one-based.

Scope:global.

Type:optional.

Intent: in.

Specified as: an integer value 0, 1, default 0.

mg the (global) number of rows of the problem.

Scope:global.

Type:optional.

Intent: in.

Specified as: an integer value. It is required if parts or repl is specified, it is optional if vg is specified.

parts the subroutine that defines the partitioning scheme.

Scope:global.

Type:required.

Specified as: a subroutine.

vl Data allocation: the set of global indices vl(1:nl) belonging to the calling

process.

Scope:local.

Type:optional.

Intent: in.

Specified as: an integer array.

nl Data allocation: in a generalized block-row distribution the number of indices

belonging to the current process.

Scope:local.

Type:optional.

Intent: in.

Specified as: an integer value. May be specified together with vl.

repl Data allocation: build a replicated index space (i.e. all processes own all

indices).

 ${\bf Scope:} {\bf global.}$

Type:**optional**. Intent: **in**.

intent. III.

Specified as: the logical value .true.

globalcheck Data allocation: do global checks on the local index lists vl

Scope: global.

Type:optional.

Intent: in.

Specified as: a logical value, default: .true.

lidx Data allocation: the set of local indices lidx(1:nl) to be assigned to the

global indices vl.

Scope:local.

Type:optional.

Intent: in.

Specified as: an integer array.

On Return

 $\mathbf{desc}_{-}\mathbf{a}$ the communication descriptor.

Scope:local.

Type:required.

Intent: out.

Specified as: a structured data of type psb_desc_type.

info Error code.

Scope: local
Type: required
Intent: out.

An integer value; 0 means no error has been detected.

Notes

1. One of the optional arguments parts, vg, vl, nl or repl must be specified, thereby choosing the initialization strategy as follows:

parts In this case we have a subroutine specifying the mapping between global indices and process/local index pairs. If this optional argument is specified, then it is mandatory to specify the argument mg as well. The subroutine must conform to the following interface:

```
interface
```

subroutine psb_parts(glob_index,mg,np,pv,nv)

```
integer, intent (in) :: glob_index,np,mg
integer, intent (out) :: nv, pv(*)
end subroutine psb_parts
end interface
```

The input arguments are:

glob_index The global index to be mapped;

np The number of processes in the mapping;

mg The total number of global rows in the mapping;

The output arguments are:

- **nv** The number of entries in pv;
- **pv** A vector containing the indices of the processes to which the global index should be assigned; each entry must satisfy $0 \le pv(i) < np$; if nv > 1 we have an index assigned to multiple processes, i.e. we have an overlap among the subdomains.
- vg In this case the association between an index and a process is specified via an integer vector vg(1:mg); each index $i \in \{1...mg\}$ is assigned to process vg(i). The vector vg must be identical on all calling processes; its entries may have the ranges (0...np-1) or (1...np) according to the value of flag. The size mg may be specified via the optional argument mg; the default is to use the entire vector vg, thus having vg-size(vg).
- vl In this case we are specifying the list of indices vl(1:nl) assigned to the current process; thus, the global problem size mg is given by the range of the aggregate of the individual vectors vl specified in the calling processes. The size may be specified via the optional argument nl; the default is to use the entire vector vl, thus having nl=size(vl). If globalcheck=.true. the subroutine will check how many times each entry in the global index space $(1 \dots mg)$ is specified in the input lists vl, thus allowing for the presence of overlap in the input, and checking for "orphan" indices. If globalcheck=.false., the subroutine will not check for overlap, and may be significantly faster, but the user is implicitly guaranteeing that there are neither orphan nor overlap indices.
- lidx The optional argument lidx is available for those cases in which the user has already established a global-to-local mapping; if it is specified, each index in vl(i) will be mapped to the corresponding local index lidx(i). When specifying the argument lidx the user would also likely employ lidx in calls to psb_cdins and local in calls to psb_spins and psb_geins; see also sec. 2.3.1.
- nl If this argument is specified alone (i.e. without v1) the result is a generalized row-block distribution in which each process I gets assigned a consecutive chunk of $N_I = nl$ global indices.
- **repl** This arguments specifies to replicate all indices on all processes. This is a special purpose data allocation that is useful in the construction of some multilevel preconditioners.
- 2. On exit from this routine the descriptor is in the build state.

- 3. Calling the routine with vg or parts implies that every process will scan the entire index space to figure out the local indices.
- 4. Overlapped indices are possible with both parts and vl invocations.
- 5. When the subroutine is invoked with vl in conjunction with globalcheck=.true., it will perform a scan of the index space to search for overlap or orphan indices.
- 6. When the subroutine is invoked with vl in conjunction with globalcheck=.false., no index space scan will take place. Thus it is the responsibility of the user to make sure that the indices specified in vl have neither orphans nor overlaps; if this assumption fails, results will be unpredictable.
- 7. Orphan and overlap indices are impossible by construction when the subroutine is invoked with nl (alone), or vg.

psb_cdins — Communication descriptor insert routine

```
call psb_cdins(nz, ia, ja, desc_a, info [,ila,jla])
call psb_cdins(nz,ja,desc,info[,jla,mask,lidx])
```

This subroutine examines the edges of the graph associated with the discretization mesh (and isomorphic to the sparsity pattern of a linear system coefficient matrix), storing them as necessary into the communication descriptor. In the first form the edges are specified as pairs of indices ia(i), ja(i); the starting index ia(i) should belong to the current process. In the second form only the remote indices ja(i) are specified.

Type: Asynchronous.

On Entry

nz the number of points being inserted.

Scope: local.
Type: required.
Intent: in.

Specified as: an integer value.

ia the indices of the starting vertex of the edges being inserted.

Scope: local.
Type: required.
Intent: in.

Specified as: an integer array of length nz.

ja the indices of the end vertex of the edges being inserted.

Scope: local.
Type: required.
Intent: in.

Specified as: an integer array of length nz.

mask Mask entries in ja, they are inserted only when the corresponding mask

entries are .true. Scope: local. Type: optional. Intent: in.

Specified as: a logical array of length nz, default .true..

lidx User defined local indices for ja.

Scope: local. Type: optional. Intent: in.

Specified as: an integer array of length nz.

On Return

desc_a the updated communication descriptor.

Scope:local.
Type:required.
Intent: inout.

Specified as: a structured data of type psb_desc_type.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

ila the local indices of the starting vertex of the edges being inserted.

Scope: local.
Type: optional.
Intent: out.

Specified as: an integer array of length nz.

jla the local indices of the end vertex of the edges being inserted.

Scope: **local**. Type: **optional**. Intent: **out**.

Specified as: an integer array of length nz.

Notes

1. This routine may only be called if the descriptor is in the build state;

- 2. This routine automatically ignores edges that do not insist on the current process, i.e. edges for which neither the starting nor the end vertex belong to the current process.
- 3. The second form of this routine will be useful when dealing with user-specified index mappings; see also 2.3.1.

psb_cdasb — Communication descriptor assembly routine

```
call psb_cdasb(desc_a, info [, mold])
```

Type: Synchronous.

On Entry

 $\mathbf{desc}_{-\mathbf{a}}$ the communication descriptor.

Scope:local.
Type:required.
Intent: inout.

Specified as: a structured data of type psb_desc_type.

mold The desired dynamic type for the internal index storage.

Scope: local. Type: optional. Intent: in.

Specified as: a object of type derived from (integer) psb_T_base_vect_type.

On Return

 $\mathbf{desc}_{-\mathbf{a}}$ the communication descriptor.

Scope:local.
Type:required.
Intent: inout.

Specified as: a structured data of type psb_desc_type.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

Notes

1. On exit from this routine the descriptor is in the assembled state.

psb_cdcpy — Copies a communication descriptor

call psb_cdcpy(desc_in, desc_out, info)

Type: Asynchronous.

On Entry

 $\mathbf{desc_in}\;\;\mathbf{the}\;\mathbf{communication}\;\mathbf{descriptor}.$

Scope:local.
Type:required.

Intent: in.

Specified as: a structured data of type psb_desc_type.

On Return

 $\mathbf{desc_out}$ the communication descriptor copy.

Scope:local.
Type:required.
Intent: out.

Specified as: a structured data of type psb_desc_type.

info Error code.

Scope: local
Type: required
Intent: out.

psb_cdfree — Frees a communication descriptor

call psb_cdfree(desc_a, info)

Type: Synchronous.

On Entry

 $\mathbf{desc_a}$ the communication descriptor to be freed.

Scope:local.
Type:required.
Intent: inout.

Specified as: a structured data of type psb_desc_type.

On Return

info Error code.

Scope: local
Type: required
Intent: out.

$psb_cdbldext$ — Build an extended communication descriptor

```
call psb_cdbldext(a,desc_a,nl,desc_out, info, extype)
```

This subroutine builds an extended communication descriptor, based on the input descriptor desc_a and on the stencil specified through the input sparse matrix a.

Type: Synchronous.

On Entry

a A sparse matrix Scope:local.

Type:required.

Intent: in.

Specified as: a structured data type.

 $\mathbf{desc_a}$ the communication descriptor.

Scope:local.

Type:required.

Intent: in.

Specified as: a structured data of type psb_Tspmat_type.

nl the number of additional layers desired.

Scope:global.

Type:required.

Intent: in.

Specified as: an integer value $nl \geq 0$.

extype the kind of estension required.

Scope:global.

Type:optional.

Intent: in.

Specified as: an integer value $psb_ovt_xhal_$, $psb_ovt_asov_$, default:

psb_ovt_xhal_

On Return

 $\mathbf{desc_out}$ the extended communication descriptor.

Scope: local.

Type:required.

Intent: inout.

Specified as: a structured data of type psb_desc_type.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

- 1. Specifying psb_ovt_xhal_ for the extype argument the user will obtain a descriptor for a domain partition in which the additional layers are fetched as part of an (extended) halo; however the index-to-process mapping is identical to that of the base descriptor;
- 2. Specifying psb_ovt_asov_ for the extype argument the user will obtain a descriptor with an overlapped decomposition: the additional layer is aggregated to the local subdomain (and thus is an overlap), and a new halo extending beyond the last additional layer is formed.

psb_spall — Allocates a sparse matrix

call psb_spall(a, desc_a, info, nnz)

Type: Synchronous.

On Entry

desc_a the communication descriptor.

Scope:local.
Type:required.
Intent: in.

Specified as: a structured data of type psb_desc_type.

nnz An estimate of the number of nonzeroes in the local part of the assembled matrix.

Scope: global.
Type: optional.
Intent: in.

Specified as: an integer value.

On Return

a the matrix to be allocated.

Scope:local
Type:required
Intent: out.

Specified as: a structured data of type psb_Tspmat_type.

info Error code.

Scope: local
Type: required
Intent: out.

An integer value; 0 means no error has been detected.

- 1. On exit from this routine the sparse matrix is in the build state.
- 2. The descriptor may be in either the build or assembled state.
- 3. Providing a good estimate for the number of nonzeroes nnz in the assembled matrix may substantially improve performance in the matrix build phase, as it will reduce or eliminate the need for (potentially multiple) data reallocations.

psb_spins — Insert a cloud of elements into a sparse matrix

call psb_spins(nz, ia, ja, val, a, desc_a, info [,local])

Type: Asynchronous.

On Entry

nz the number of elements to be inserted.

Scope: local.

 ${\bf Type:} {\bf required}.$

Intent: in.

Specified as: an integer scalar.

ia the row indices of the elements to be inserted.

Scope:local.

Type:required.

Intent: in.

Specified as: an integer array of size nz.

ja the column indices of the elements to be inserted.

Scope:local.

Type:required.

Intent: in.

Specified as: an integer array of size nz.

val the elements to be inserted.

Scope:local.

Type:required.

Intent: in.

Specified as: an array of size nz. Must be of the same type and kind of the coefficients of the sparse matrix a.

 $\mathbf{desc}_{-\mathbf{a}}$ The communication descriptor.

Scope: local.
Type: required.
Intent: inout.

Specified as: a variable of type psb_desc_type.

local Whether the entries in the indices vectors ia, ja are already in local

numbering. Scope:**local**. Type:**optional**.

Specified as: a logical value; default: .false..

On Return

a the matrix into which elements will be inserted.

Scope:local
Type:required
Intent: inout.

Specified as: a structured data of type ${\tt psb_Tspmat_type}.$

 $\mathbf{desc_a}$ The communication descriptor.

Scope: local.
Type: required.
Intent: inout.

Specified as: a variable of type psb_desc_type.

info Error code.

Scope: local
Type: required
Intent: out.

An integer value; 0 means no error has been detected.

- 1. On entry to this routine the descriptor may be in either the build or assembled state.
- 2. On entry to this routine the sparse matrix may be in either the build or update state.
- 3. If the descriptor is in the build state, then the sparse matrix must also be in the build state; the action of the routine is to (implicitly) call psb_cdins to add entries to the sparsity pattern; each sparse matrix entry implicitly defines a graph edge, that is passed to the descriptor routine for the appropriate processing;
- 4. The coefficients to be inserted are represented by the ordered triples ia(i), ja(i), val(i), for i = 1, ..., nz; these triples should belong to the current process, i.e. ia(i) should be one of the local indices, but are otherwise arbitrary;
- 5. There is no requirement that a given row must be passed in its entirety to a single call to this routine: the buildup of a row may be split into as many calls as desired;
- 6. Coefficients from different rows may also be mixed up freely in a single call, according to the application needs;
- 7. Any coefficients from matrix rows not owned by the calling process are silently ignored;
- 8. If the descriptor is in the assembled state, then any entries in the sparse matrix that would generate additional communication requirements are ignored;
- 9. If the matrix is in the update state, any entries in positions that were not present in the original matrix are ignored.

```
psb_spasb — Sparse matrix assembly routine
call psb_spasb(a, desc_a, info, afmt, upd, dupl, mold)
Type: Synchronous.
On Entry
\mathbf{desc}_{-\mathbf{a}} the communication descriptor.
     Scope:local.
     Type:required.
     Intent: in.
     Specified as: a structured data of type psb_desc_type.
afmt the storage format for the sparse matrix.
     Scope: local.
     Type: optional.
     Intent: in.
     Specified as: an array of characters. Defalt: 'CSR'.
upd Provide for updates to the matrix coefficients.
     Scope: global.
     Type: optional.
     Intent: in.
     Specified as: integer, possible values: psb_upd_srch_, psb_upd_perm_
dupl How to handle duplicate coefficients.
     Scope: global.
     Type: optional.
     Intent: in.
     Specified as: integer, possible values: psb_dupl_ovwrt_, psb_dupl_add_,
     psb_dupl_err_.
mold The desired dynamic type for the internal matrix storage.
     Scope: local.
     Type: optional.
     Intent: in.
     Specified as: an object of a class derived from psb_T_base_sparse_mat.
On Return
a the matrix to be assembled.
     Scope:local
     Type:required
     Intent: inout.
     Specified as: a structured data of type psb_Tspmat_type.
info Error code.
     Scope: local
     Type: required
     Intent: out.
     An integer value; 0 means no error has been detected.
```

- 1. On entry to this routine the descriptor must be in the assembled state, i.e. psb_cdasb must already have been called.
- 2. The sparse matrix may be in either the build or update state;
- 3. Duplicate entries are detected and handled in both build and update state, with the exception of the error action that is only taken in the build state, i.e. on the first assembly;
- 4. If the update choice is psb_upd_perm_, then subsequent calls to psb_spins to update the matrix must be arranged in such a way as to produce exactly the same sequence of coefficient values as encountered at the first assembly;
- 5. The output storage format need not be the same on all processes;
- 6. On exit from this routine the matrix is in the assembled state, and thus is suitable for the computational routines.

psb_spfree — Frees a sparse matrix

```
call psb_spfree(a, desc_a, info)
```

Type: Synchronous.

On Entry

a the matrix to be freed.

Scope:local
Type:required
Intent: inout.

Specified as: a structured data of type psb_Tspmat_type.

 $\mathbf{desc}_{-\mathbf{a}}$ the communication descriptor.

Scope:local.
Type:required.
Intent: in.

Specified as: a structured data of type psb_desc_type.

On Return

info Error code.

Scope: local
Type: required
Intent: out.

psb_sprn — Reinit sparse matrix structure for psblas routines.

```
call psb_sprn(a, decsc_a, info, clear)
```

Type: Synchronous.

On Entry

a the matrix to be reinitialized.

Scope:local
Type:required
Intent: inout.

Specified as: a structured data of type psb_Tspmat_type.

 $\mathbf{desc}_\mathbf{a}$ the communication descriptor.

Scope:local.
Type:required.
Intent: in.

Specified as: a structured data of type psb_desc_type.

clear Choose whether to zero out matrix coefficients

Scope:**local**. Type:**optional**. Intent: **in**. Default: true.

On Return

info Error code.

Scope: local
Type: required
Intent: out.

An integer value; 0 means no error has been detected.

Notes

1. On exit from this routine the sparse matrix is in the update state.

psb_geall — Allocates a dense matrix

call psb_geall(x, desc_a, info, n, lb)

Type: Synchronous.

On Entry

 $\mathbf{desc}_{-\mathbf{a}}$ The communication descriptor.

Scope: local
Type: required
Intent: in.

Specified as: a variable of type psb_desc_type.

n The number of columns of the dense matrix to be allocated.

Scope: local
Type: optional
Intent: in.

Specified as: Integer scalar, default 1. It is not a valid argument if x is a

rank-1 array.

lb The lower bound for the column index range of the dense matrix to be allocated.

Scope: local
Type: optional
Intent: in.

Specified as: Integer scalar, default 1. It is not a valid argument if x is a

rank-1 array.

On Return

 ${f x}$ The dense matrix to be allocated.

Scope: local
Type: required
Intent: out.

Specified as: a rank one or two array with the ALLOCATABLE attribute or an object of type psb_T_vect_type, of type real, complex or integer.

info Error code.

Scope: local
Type: required
Intent: out.

```
psb_geins — Dense matrix insertion routine
```

call psb_geins(m, irw, val, x, desc_a, info [,dupl,local])

Type: Asynchronous.

On Entry

m Number of rows in *val* to be inserted.

Scope:local.
Type:required.

Intent: in.

Specified as: an integer value.

irw Indices of the rows to be inserted. Specifically, row i of val will be inserted into the local row corresponding to the global row index irw(i).

Scope:local.
Type:required.

Intent: in.

Specified as: an integer array.

val the dense submatrix to be inserted.

Scope:local.
Type:required.

Intent: in.

Specified as: a rank 1 or 2 array. Specified as: an integer value.

desc_a the communication descriptor.

Scope: local.

Type:required.

Intent: in.

Specified as: a structured data of type psb_desc_type.

dupl How to handle duplicate coefficients.

Scope: **global**. Type: **optional**.

Intent: in.

Specified as: integer, possible values: psb_dupl_ovwrt_, psb_dupl_add_.

local Whether the entries in the index vector irw, are already in local number-

ing.

Scope:local.

Type:optional.

Specified as: a logical value; default: .false..

On Return

 \mathbf{x} the output dense matrix.

Scope: local Type: required Intent: inout.

Specified as: a rank one or two array or an object of type ${\tt psb_T_vect_type},$

of type real, complex or integer.

info Error code.

Scope: local
Type: required
Intent: out.

An integer value; 0 means no error has been detected.

Notes

 $1.\ \,$ Dense vectors/matrices do not have an associated state;

 $2.\,$ Duplicate entries are either overwritten or added, there is no provision for raising an error condition.

psb_geasb — Assembly a dense matrix

call psb_geasb(x, desc_a, info, mold)

Type: Synchronous.

On Entry

 $\mathbf{desc_a}$ The communication descriptor.

Scope: local
Type: required
Intent: in.

Specified as: a variable of type psb_desc_type.

mold The desired dynamic type for the internal vector storage.

Scope: local.
Type: optional.
Intent: in.

Specified as: an object of a class derived from psb_T_base_vect_type; this

is only allowed when x is of type $psb_T_vect_type$.

On Return

 \mathbf{x} The dense matrix to be assembled.

Scope: local
Type: required
Intent: inout.

Specified as: a rank one or two array with the ALLOCATABLE or an

object of type psb_T_vect_type, of type real, complex or integer.

info Error code.

Scope: local Type: required Intent: out.

psb_gefree — Frees a dense matrix

call psb_gefree(x, desc_a, info)

Type: Synchronous.

On Entry

 \mathbf{x} The dense matrix to be freed.

Scope: local
Type: required
Intent: inout.

Specified as: a rank one or two array with the ALLOCATABLE or an

object of type psb_T_vect_type, of type real, complex or integer.

 $\mathbf{desc}_{-}\mathbf{a}$ The communication descriptor.

Scope: local
Type: required
Intent: in.

Specified as: a variable of type psb_desc_type.

On Return

info Error code.

Scope: local Type: required Intent: out.

psb_gelp — Applies a left permutation to a dense matrix

call psb_gelp(trans, iperm, x, info)

Type: Asynchronous.

On Entry

trans A character that specifies whether to permute A or A^T .

Scope: local
Type: required
Intent: in.

Specified as: a single character with value 'N' for A or 'T' for A^T .

iperm An integer array containing permutation information.

Scope: local
Type: required
Intent: in.

Specified as: an integer one-dimensional array.

 \mathbf{x} The dense matrix to be permuted.

Scope: local Type: required Intent: inout.

Specified as: a one or two dimensional array.

On Return

info Error code.

Scope: local
Type: required
Intent: out.

psb_glob_to_loc — Global to local indices convertion

call psb_glob_to_loc(x, y, desc_a, info, iact,owned)
call psb_glob_to_loc(x, desc_a, info, iact,owned)

Type: Asynchronous.

On Entry

 \mathbf{x} An integer vector of indices to be converted.

Scope: local
Type: required
Intent: in, inout.

Specified as: a rank one integer array.

desc_a the communication descriptor.

Scope:local.
Type:required.

Intent: in.

Specified as: a structured data of type psb_desc_type.

iact specifies action to be taken in case of range errors. Scope: global

Type: **optional** Intent: **in**.

Specified as: a character variable Ignore, Warning or Abort, default Ignore.

owned Specfies valid range of input Scope: global

Type: **optional** Intent: **in**.

If true, then only indices strictly owned by the current process are considered valid, if false then halo indices are also accepted. Default: false.

On Return

 \mathbf{x} If y is not present, then x is overwritten with the translated integer indices.

Scope: **global**Type: **required**Intent: **inout**.

Specified as: a rank one integer array.

y If y is present, then y is overwritten with the translated integer indices, and

x is left unchanged. Scope: **global**

Type: **optional** Intent: **out**.

Specified as: a rank one integer array.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

- 1. If an input index is out of range, then the corresponding output index is set to a negative number;
- 2. The default Ignore means that the negative output is the only action taken on an out-of-range input.

psb_loc_to_glob — Local to global indices conversion

```
call psb_loc_to_glob(x, y, desc_a, info, iact)
call psb_loc_to_glob(x, desc_a, info, iact)
```

Type: Asynchronous.

On Entry

 \mathbf{x} An integer vector of indices to be converted.

Scope: local
Type: required
Intent: in, inout.

Specified as: a rank one integer array.

 $\mathbf{desc}_{-\mathbf{a}}$ the communication descriptor.

Scope:local.
Type:required.
Intent: in.

Specified as: a structured data of type psb_desc_type.

iact specifies action to be taken in case of range errors. Scope: global

Type: **optional** Intent: **in**.

Specified as: a character variable Ignore, Warning or Abort, default Ignore.

On Return

 \mathbf{x} If y is not present, then x is overwritten with the translated integer indices.

Scope: **global**Type: **required**Intent: **inout**.

Specified as: a rank one integer array.

 \mathbf{y} If y is not present, then y is overwritten with the translated integer indices,

and x is left unchanged. Scope: **global**

Type: **optional** Intent: **out**.

Specified as: a rank one integer array.

info Error code.

Scope: local
Type: required
Intent: out.

psb_is_owned —

call psb_is_owned(x, desc_a)

Type: Asynchronous.

On Entry

 \mathbf{x} Integer index.

Scope: local
Type: required
Intent: in.

Specified as: a scalar integer.

 $\mathbf{desc}_{-\mathbf{a}}$ the communication descriptor.

Scope:local.
Type:required.

Intent: in.

Specified as: a structured data of type psb_desc_type.

On Return

Function value A logical mask which is true if x is owned by the current pro-

cess Scope: local
Type: required
Intent: out.

Notes

1. This routine returns a .true. value for an index that is strictly owned by the current process, excluding the halo indices

psb_owned_index —

call psb_owned_index(y, x, desc_a, info)

Type: Asynchronous.

On Entry

 \mathbf{x} Integer indices.

Scope: local
Type: required
Intent: in, inout.

Specified as: a scalar or a rank one integer array.

 $\mathbf{desc}_{-\mathbf{a}}$ the communication descriptor.

Scope:local.
Type:required.

Intent: in.

Specified as: a structured data of type psb_desc_type.

iact specifies action to be taken in case of range errors. Scope: global

Type: **optional** Intent: **in**.

Specified as: a character variable Ignore, Warning or Abort, default Ignore.

On Return

 \mathbf{y} A logical mask which is true for all corresponding entries of x that are owned

by the current process Scope: local

Type: **required** Intent: **out**.

Specified as: a scalar or rank one logical array.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

Notes

1. This routine returns a .true. value for those indices that are strictly owned by the current process, excluding the halo indices

psb_is_local —

call psb_is_local(x, desc_a)

Type: Asynchronous.

On Entry

 \mathbf{x} Integer index.

Scope: local
Type: required
Intent: in.

Specified as: a scalar integer.

 $\mathbf{desc_a}$ the communication descriptor.

Scope:local.
Type:required.

Intent: in.

Specified as: a structured data of type psb_desc_type.

On Return

Function value A logical mask which is true if x is local to the current process

Scope: local Type: required Intent: out.

Notes

1. This routine returns a .true. value for an index that is local to the current process, including the halo indices

psb_local_index —

call psb_local_index(y, x, desc_a, info)

Type: Asynchronous.

On Entry

 \mathbf{x} Integer indices.

Scope: local
Type: required
Intent: in, inout.

Specified as: a scalar or a rank one integer array.

 $\mathbf{desc}_{-\mathbf{a}}$ the communication descriptor.

Scope:local.
Type:required.

Intent: in.

Specified as: a structured data of type psb_desc_type.

iact specifies action to be taken in case of range errors. Scope: global

Type: **optional** Intent: **in**.

Specified as: a character variable Ignore, Warning or Abort, default Ignore.

On Return

 \mathbf{y} A logical mask which is true for all corresponding entries of x that are local

to the current process Scope: local

Type: **required** Intent: **out**.

Specified as: a scalar or rank one logical array.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

Notes

1. This routine returns a .true. value for those indices that are local to the current process, including the halo indices.

psb_get_boundary — Extract list of boundary elements

call psb_get_boundary(bndel, desc, info)

Type: Asynchronous.

On Entry

desc the communication descriptor.

Scope:local.
Type:required.
Intent: in.

Specified as: a structured data of type psb_desc_type.

On Return

bndel The list of boundary elements on the calling process, in local numbering.

Scope: local Type: required Intent: out.

Specified as: a rank one array with the ALLOCATABLE attribute, of

type integer.

info Error code.

Scope: local
Type: required
Intent: out.

An integer value; 0 means no error has been detected.

- 1. If there are no boundary elements (i.e., if the local part of the connectivity graph is self-contained) the output vector is set to the "not allocated" state.
- 2. Otherwise the size of bndel will be exactly equal to the number of boundary elements.

psb_get_overlap — Extract list of overlap elements

call psb_get_overlap(ovrel, desc, info)

Type: Asynchronous.

On Entry

desc the communication descriptor.

Scope:local.
Type:required.
Intent: in.

Specified as: a structured data of type psb_desc_type.

On Return

ovrel The list of overlap elements on the calling process, in local numbering.

Scope: local
Type: required
Intent: out.

Specified as: a rank one array with the ALLOCATABLE attribute, of

type integer.

info Error code.

Scope: local
Type: required
Intent: out.

An integer value; 0 means no error has been detected.

- 1. If there are no overlap elements the output vector is set to the "not allocated" state.
- 2. Otherwise the size of ovrel will be exactly equal to the number of overlap elements.

```
psb_sp_getrow — Extract row(s) from a sparse matrix
```

Type: Asynchronous.

On Entry

row The (first) row to be extracted.

 $\begin{array}{c} \textbf{Scope:} \textbf{local} \\ \textbf{Type:} \textbf{required} \end{array}$

Intent: in.

Specified as: an integer > 0.

a the matrix from which to get rows.

Scope:local Type:required

Intent: in.

Specified as: a structured data of type psb_Tspmat_type.

append Whether to append or overwrite existing output.

Scope:local Type:optional

Intent: in.

Specified as: a logical value default: false (overwrite).

nzin Input size to be appended to.

Scope:local

 ${\bf Type:} {\bf optional}$

Intent: in.

Specified as: an integer > 0. When append is true, specifies how many entries in the output vectors are already filled.

lrw The last row to be extracted.

 ${\bf Scope:} {\bf local}$

Type:optional

Intent: in.

Specified as: an integer > 0, default: row.

On Return

nz the number of elements returned by this call.

Scope:local.

 ${\bf Type:} {\bf required}.$

Intent: out.

Returned as: an integer scalar.

ia the row indices.

Scope:local.

Type:required.

Intent: inout.

Specified as: an integer array with the ALLOCATABLE attribute.

ja the column indices of the elements to be inserted.

Scope:local.
Type:required.
Intent: inout.

Specified as: an integer array with the ALLOCATABLE attribute.

val the elements to be inserted.

Scope:local.
Type:required.
Intent: inout.

Specified as: a real array with the ALLOCATABLE attribute.

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

- The output nz is always the size of the output generated by the current call; thus, if append=.true., the total output size will be nzin+nz, with the newly extracted coefficients stored in entries nzin+1:nzin+nz of the array arguments;
- 2. When append=.true. the output arrays are reallocated as necessary;
- 3. The row and column indices are returned in the local numbering scheme; if the global numbering is desired, the user may employ the psb_loc_to_glob routine on the output.

psb_sizeof — Memory occupation

This function computes the memory occupation of a PSBLAS object.

```
isz = psb_sizeof(a)
isz = psb_sizeof(desc_a)
isz = psb_sizeof(prec)
```

Type: Asynchronous.

On Entry

a A sparse matrix A. Scope: local Type: required Intent: in.

Specified as: a structured data of type psb_Tspmat_type.

 $\mathbf{desc_a}$ Communication descriptor.

Scope: local Type: required Intent: in.

Specified as: a structured data of type psb_desc_type.

prec Scope: local Type: required

Intent: in.

Specified as: a preconditioner data structure psb_prec_type.

On Return

Function value The memory occupation of the object specified in the calling

sequence, in bytes. Scope: local

Returned as: an integer(psb_long_int_k_) number.

Sorting utilities —

```
psb_msort — Sorting by the Merge-sort algorithm
psb_qsort — Sorting by the Quicksort algorithm
psb_hsort — Sorting by the Heapsort algorithm
call psb_msort(x,ix,dir,flag)
call psb_qsort(x,ix,dir,flag)
call psb_hsort(x,ix,dir,flag)
```

These serial routines sort a sequence X into ascending or descending order. The argument meaning is identical for the three calls; the only difference is the algorithm used to accomplish the task (see Usage Notes below).

Type: Asynchronous.

On Entry

 \mathbf{x} The sequence to be sorted.

Type:required.

Specified as: an integer, real or complex array of rank 1.

ix A vector of indices.

Type:optional.

Specified as: an integer array of (at least) the same size as X.

dir The desired ordering.

Type:optional.

Specified as: an integer value:

```
Integer and real data: psb_sort_up_, psb_sort_down_, psb_asort_up_,
    psb_asort_down_; default psb_sort_up_.
```

 $\begin{tabular}{ll} \bf Complex\ data:\ psb_lsort_up_,\ psb_lsort_down_,\ psb_asort_up_,\ psb_asort_down_;\ default\ psb_lsort_up_. \end{tabular}$

flag Whether to keep the original values in IX.

Type:optional.

Specified as: an integer value psb_sort_ovw_idx_ or psb_sort_keep_idx_; default psb_sort_ovw_idx_.

On Return

x The sequence of values, in the chosen ordering.

Type:required.

Specified as: an integer, real or complex array of rank 1.

ix A vector of indices.

Type: Optional

An integer array of rank 1, whose entries are moved to the same position as the corresponding entries in x.

- 1. For integer or real data the sorting can be performed in the up/down direction, on the natural or absolute values;
- 2. For complex data the sorting can be done in a lexicographic order (i.e.: sort on the real part with ties broken according to the imaginary part) or on the absolute values;
- 3. The routines return the items in the chosen ordering; the output difference is the handling of ties (i.e. items with an equal value) in the original input. With the merge-sort algorithm ties are preserved in the same relative order as they had in the original sequence, while this is not guaranteed for quicksort or heapsort;
- 4. If $flag = psb_sort_ovw_idx_$ then the entries in ix(1:n) where n is the size of x are initialized to $ix(i) \leftarrow i$; thus, upon return from the subroutine, for each index i we have in ix(i) the position that the item x(i) occupied in the original data sequence;
- 5. If $flag = psb_sort_keep_idx$ the routine will assume that the entries in ix(:) have already been initialized by the user;
- 6. The three sorting algorithms have a similar $O(n \log n)$ expected running time; in the average case quicksort will be the fastest and merge-sort the slowest. However note that:
 - (a) The worst case running time for quicksort is $O(n^2)$; the algorithm implemented here follows the well-known median-of-three heuristics, but the worst case may still apply;
 - (b) The worst case running time for merge-sort and heap-sort is $O(n \log n)$ as the average case;
 - (c) The merge-sort algorithm is implemented to take advantage of sub-sequences that may be already in the desired ordering prior to the subroutine call; this situation is relatively common when dealing with groups of indices of sparse matrix entries, thus merge-sort is the preferred choice when a sorting is needed by other routines in the library.

7 Parallel environment routines

psb_init — Initializes PSBLAS parallel environment

```
call psb_init(icontxt, np, basectxt, ids)
```

This subroutine initializes the PSBLAS parallel environment, defining a virtual parallel machine.

Type: Synchronous.

On Entry

np Number of processes in the PSBLAS virtual parallel machine.

Scope: **global**. Type: **optional**. Intent: **in**.

Specified as: an integer value. Default: use all available processes.

basectxt the initial communication context. The new context will be defined from the processes participating in the initial one.

Scope: **global**. Type: **optional**. Intent: **in**.

Specified as: an integer value. Default: use MPI_COMM_WORLD.

ids Identities of the processes to use for the new context; the argument is ignored when np is not specified. This allows the processes in the new environment to be in an order different from the original one.

Scope: **global**. Type: **optional**. Intent: **in**.

Specified as: an integer array. Default: use the indices $(0 \dots np - 1)$.

On Return

icontxt the communication context identifying the virtual parallel machine. Note that this is always a duplicate of basectxt, so that library communications are completely separated from other communication operations.

Scope: **global**. Type: **required**. Intent: **out**.

Specified as: an integer variable.

- 1. A call to this routine must precede any other PSBLAS call.
- 2. It is an error to specify a value for np greater than the number of processes available in the underlying base parallel environment.

psb_info — Return information about PSBLAS parallel environment

```
call psb_info(icontxt, iam, np)
```

This subroutine returns information about the PSBLAS parallel environment, defining a virtual parallel machine.

Type: Asynchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**.

Intent: in.

Specified as: an integer variable.

On Return

iam Identifier of current process in the PSBLAS virtual parallel machine.

Scope: local.
Type: required.
Intent: out.

Specified as: an integer value. $-1 \le iam \le np - 1$

np Number of processes in the PSBLAS virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **out**.

Specified as: an integer variable.

- 1. For processes in the virtual parallel machine the identifier will satisfy $0 \le iam \le np-1$;
- 2. If the user has requested on psb_i a number of processes less than the total available in the parallel execution environment, the remaining processes will have on return iam = -1; the only call involving icontxt that any such process may execute is to psb_e .

psb_exit — Exit from PSBLAS parallel environment

```
call psb_exit(icontxt)
call psb_exit(icontxt,close)
```

This subroutine exits from the PSBLAS parallel virtual machine.

Type: Synchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer variable.

close Whether to close all data structures related to the virtual parallel machine, besides those associated with icontxt.

Scope: **global**. Type: **optional**. Intent: **in**.

Specified as: a logical variable, default value: true.

- 1. This routine may be called even if a previous call to psb_info has returned with iam = -1; indeed, it it is the only routine that may be called with argument icontxt in this situation.
- 2. A call to this routine with close=.true. implies a call to MPI_Finalize, after which no parallel routine may be called.
- 3. If the user whishes to use multiple communication contexts in the same program, or to enter and exit multiple times into the parallel environment, this routine may be called to selectively close the contexts with close=.false., while on the last call it should be called with close=.true. to shutdown in a clean way the entire parallel environment.

$psb_get_mpicomm$ — Get the MPI communicator

call psb_get_mpicomm(icontxt, icomm)

This subroutine returns the MPI communicator associated with a PSBLAS context $\,$

Type: Asynchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer variable.

On Return

 ${\bf icomm}$ The MPI communicator associated with the PSBLAS virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **out**.

psb_get_rank — Get the MPI rank

```
call psb_get_rank(rank, icontxt, id)
```

This subroutine returns the MPI rank of the PSBLAS process id

Type: Asynchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer variable.

id Identifier of a process in the PSBLAS virtual parallel machine.

Scope: local.
Type: required.

Intent: in.

Specified as: an integer value. $0 \le id \le np - 1$

On Return

rank The MPI rank associated with the PSBLAS process id.

Scope: local.
Type: required.
Intent: out.

$psb_wtime - Wall clock timing$

time = psb_wtime()

This function returns a wall clock timer. The resolution of the timer is dependent on the underlying parallel environment implementation.

Type: Asynchronous.

On Exit

Function value the elapsed time in seconds.

Returned as: a real(psb_dpk_) variable.

psb_barrier — Sinchronization point parallel environment

call psb_barrier(icontxt)

This subroutine acts as an explicit synchronization point for the PSBLAS parallel virtual machine.

Type: Synchronous.

On Entry

 ${\bf icontxt}$ the communication context identifying the virtual parallel machine.

Scope: **global**.

Type: **required**.

Intent: in.

Specified as: an integer variable.

psb_abort — Abort a computation

call psb_abort(icontxt)

This subroutine aborts computation on the parallel virtual machine.

Type: Asynchronous.

On Entry

 ${\bf icontxt}$ the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer variable.

psb_bcast — Broadcast data

call psb_bcast(icontxt, dat, root)

This subroutine implements a broadcast operation based on the underlying communication library.

Type: Synchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer variable.

dat On the root process, the data to be broadcast.

Scope: **global**. Type: **required**. Intent: **inout**.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array, or a character or logical variable, which may be a scalar or rank 1 array. Type, kind, rank and size must agree on all processes.

root Root process holding data to be broadcast.

Scope: **global**. Type: **optional**. Intent: **in**.

Specified as: an integer value $0 \le root \le np - 1$, default 0

On Return

dat On processes other than root, the data to be broadcast.

Scope: **global**. Type: **required**. Intent: **inout**.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array, or a character or logical scalar. Type, kind, rank and size must agree on all processes.

psb_sum — Global sum

```
call psb_sum(icontxt, dat, root)
```

This subroutine implements a sum reduction operation based on the underlying communication library.

Type: Synchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**.

Intent: in.

Specified as: an integer variable.

dat The local contribution to the global sum.

Scope: **global**. Type: **required**. Intent: **inout**.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array. Type, kind, rank and size must agree on all processes.

processes.

root Process to hold the final sum, or -1 to make it available on all processes.

Scope: **global**. Type: **optional**.

Intent: in.

Specified as: an integer value $-1 \le root \le np - 1$, default -1.

On Return

dat On destination process(es), the result of the sum operation.

Scope: **global**. Type: **required**. Intent: **inout**.

Specified as: an integer, real or complex variable, which may be a scalar,

or a rank 1 or 2 array.

Type, kind, rank and size must agree on all processes.

- 1. The dat argument is both input and output, and its value may be changed even on processes different from the final result destination.
- 2. The dat argument may also be a long integer scalar.

$psb_max - Global maximum$

```
call psb_max(icontxt, dat, root)
```

This subroutine implements a maximum valuereduction operation based on the underlying communication library.

Type: Synchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**.

Type: **required**.

Intent: in.

Specified as: an integer variable.

dat The local contribution to the global maximum.

Scope: local.
Type: required.
Intent: inout.

Specified as: an integer or real variable, which may be a scalar, or a rank 1 or 2 array. Type, kind, rank and size must agree on all processes.

root Process to hold the final maximum, or -1 to make it available on all pro-

cesses.

Scope: **global**. Type: **optional**. Intent: **in**.

Specified as: an integer value $-1 \le root \le np - 1$, default -1.

On Return

dat On destination process(es), the result of the maximum operation.

Scope: **global**. Type: **required**.

Intent: in.

Specified as: an integer or real variable, which may be a scalar, or a rank 1 or 2 array. Type, kind, rank and size must agree on all processes.

- 1. The dat argument is both input and output, and its value may be changed even on processes different from the final result destination.
- 2. The dat argument may also be a long integer scalar.

psb_min — Global minimum

```
call psb_min(icontxt, dat, root)
```

This subroutine implements a minimum value reduction operation based on the underlying communication library.

Type: Synchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**.

Intent: in.

Specified as: an integer variable.

dat The local contribution to the global minimum.

Scope: **local**. Type: **required**. Intent: **inout**.

Specified as: an integer or real variable, which may be a scalar, or a rank 1 or 2 array. Type, kind, rank and size must agree on all processes.

 ${f root}$ Process to hold the final value, or -1 to make it available on all processes.

Scope: global.
Type: optional.

Intent: in.

Specified as: an integer value $-1 \le root \le np - 1$, default -1.

On Return

dat On destination process(es), the result of the minimum operation.

Scope: **global**. Type: **required**. Intent: **inout**.

Specified as: an integer or real variable, which may be a scalar, or a rank

1 or 2 array.

Type, kind, rank and size must agree on all processes.

- 1. The dat argument is both input and output, and its value may be changed even on processes different from the final result destination.
- 2. The dat argument may also be a long integer scalar.

psb_amx — Global maximum absolute value

```
call psb_amx(icontxt, dat, root)
```

This subroutine implements a maximum absolute value reduction operation based on the underlying communication library.

Type: Synchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: global. Type: required.

Intent: in.

Specified as: an integer variable.

dat The local contribution to the global maximum.

Scope: local. Type: required. Intent: inout.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array. Type, kind, rank and size must agree on all

processes.

root Process to hold the final value, or -1 to make it available on all processes.

Scope: global. Type: optional.

Intent: in.

Specified as: an integer value $-1 \le root \le np - 1$, default -1.

On Return

dat On destination process(es), the result of the maximum operation.

Scope: global. Type: required. Intent: inout.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array. Type, kind, rank and size must agree on all processes.

- 1. The dat argument is both input and output, and its value may be changed even on processes different from the final result destination.
- 2. The dat argument may also be a long integer scalar.

psb_amn — Global minimum absolute value

call psb_amn(icontxt, dat, root)

This subroutine implements a minimum absolute value reduction operation based on the underlying communication library.

Type: Synchronous.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: global.
Type: required.

Intent: in.

Specified as: an integer variable.

dat The local contribution to the global minimum.

Scope: **local**. Type: **required**. Intent: **inout**.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array. Type, kind, rank and size must agree on all

processes.

 ${f root}$ Process to hold the final value, or -1 to make it available on all processes.

Scope: **global**. Type: **optional**. Intent: **in**.

Specified as: an integer value $-1 \le root \le np - 1$, default -1.

On Return

dat On destination process(es), the result of the minimum operation.

Scope: **global**. Type: **required**. Intent: **inout**.

Specified as: an integer, real or complex variable, which may be a scalar,

or a rank 1 or 2 array.

Type, kind, rank and size must agree on all processes.

- 1. The dat argument is both input and output, and its value may be changed even on processes different from the final result destination.
- 2. The dat argument may also be a long integer scalar.

psb_snd — Send data

```
call psb_snd(icontxt, dat, dst, m)
```

This subroutine sends a packet of data to a destination.

Type: Synchronous: see usage notes.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer variable.

dat The data to be sent.

Scope: local.
Type: required.
Intent: in.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array, or a character or logical scalar. Type, kind and rank must agree on sender and receiver process; if m is not specified, size must agree as well.

dst Destination process.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer value $0 \le dst \le np - 1$.

m Number of rows.

Scope: **global**. Type: **Optional**. Intent: **in**.

Specified as: an integer value $0 \le m \le size(dat, 1)$.

When dat is a rank 2 array, specifies the number of rows to be sent independently of the leading dimension size(dat, 1); must have the same value on sending and receiving processes.

On Return

Notes

1. This subroutine implies a synchronization, but only between the calling process and the destination process dst.

psb_rcv — Receive data

```
call psb_rcv(icontxt, dat, src, m)
```

This subroutine receives a packet of data to a destination.

Type: Synchronous: see usage notes.

On Entry

icontxt the communication context identifying the virtual parallel machine.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer variable.

src Source process.

Scope: **global**. Type: **required**. Intent: **in**.

Specified as: an integer value $0 \le src \le np - 1$.

m Number of rows.

Scope: **global**.
Type: **Optional**.

Intent: in.

Specified as: an integer value $0 \le m \le size(dat, 1)$.

When dat is a rank 2 array, specifies the number of rows to be sent independently of the leading dimension size(dat, 1); must have the same value on sending and receiving processes.

On Return

dat The data to be received.

Scope: local.
Type: required.
Intent: inout.

Specified as: an integer, real or complex variable, which may be a scalar, or a rank 1 or 2 array, or a character or logical scalar. Type, kind and rank must agree on sender and receiver process; if m is not specified, size must agree as well.

Notes

1. This subroutine implies a synchronization, but only between the calling process and the source process src.

8 Error handling

The PSBLAS library error handling policy has been completely rewritten in version 2.0. The idea behind the design of this new error handling strategy is to keep error messages on a stack allowing the user to trace back up to the point where the first error message has been generated. Every routine in the PSBLAS-2.0 library has, as last non-optional argument, an integer info variable; whenever, inside the routine, an error is detected, this variable is set to a value corresponding to a specific error code. Then this error code is also pushed on the error stack and then either control is returned to the caller routine or the execution is aborted, depending on the users choice. At the time when the execution is aborted, an error message is printed on standard output with a level of verbosity than can be chosen by the user. If the execution is not aborted, then, the caller routine checks the value returned in the info variable and, if not zero, an error condition is raised. This process continues on all the levels of nested calls until the level where the user decides to abort the program execution.

Figure 9 shows the layout of a generic psb_foo routine with respect to the PSBLAS-2.0 error handling policy. It is possible to see how, whenever an error condition is detected, the info variable is set to the corresponding error code which is, then, pushed on top of the stack by means of the psb_errpush. An error condition may be directly detected inside a routine or indirectly checking the error code returned returned by a called routine. Whenever an error is encountered, after it has been pushed on stack, the program execution skips to a point where the error condition is handled; the error condition is handled either by returning control to the caller routine or by calling the psb_error routine which prints the content of the error stack and aborts the program execution, according to the choice made by the user with psb_set_erraction. The default is to print the error and terminate the program, but the user may choose to handle the error explicitly.

Figure 10 reports a sample error message generated by the PSBLAS-2.0 library. This error has been generated by the fact that the user has chosen the invalid "FOO" storage format to represent the sparse matrix. From this error message it is possible to see that the error has been detected inside the psb_cest subroutine called by psb_spasb ... by process 0 (i.e. the root process).

```
subroutine psb_foo(some args, info)
   if (error detected) then
      info=errcode1
      call psb_errpush('psb_foo', errcode1)
      goto 9999
   end if
   call psb_bar(some args, info)
   if (info .ne. zero) then
      info{=}errcode2
      call psb_errpush('psb_foo', errcode2)
      goto 9999
   end if
9999 continue
   if (err_act .eq. act_abort) then
     call psb_error(icontxt)
     return
   else
     return
   end if
end subroutine psb_foo
```

Figure 9: The layout of a generic psb_foo routine with respect to PSBLAS-2.0 error handling policy.

Figure 10: A sample PSBLAS-2.0 error message. Process 0 detected an error condition inside the psb_cest subroutine

$psb_errpush$ —Pushes an error code onto the error stack

```
call psb_errpush(err_c , r_name , i_err , a_err)
Type: Asynchronous.
On Entry
\mathbf{err}_{\mathbf{c}} the error code
     Scope: local
     Type: required
     Intent: in.
     Specified as: an integer.
r_name the soutine where the error has been caught.
     Scope: local
     Type: required
     Intent: in.
     Specified as: a string.
i\_err addional info for error code
     Scope: local
     Type: optional
     Specified as: an integer array
\mathbf{a}_err addional info for error code
     Scope: local
     Type: optional
```

Specified as: a string.

psb_error—Prints the error stack content and aborts execution

call psb_error(icontxt)

Type: Asynchronous.

On Entry

 ${\bf icontxt}$ the communication context.

Scope: **global**Type: **optional**Intent: **in**.

Specified as: an integer.

$psb_set_errverbosity—Sets$ the verbosity of error messages.

$psb_set_erraction$ —Set the type of action to be taken upon error condition.

9 Utilities

We have some utilities available for input and output of sparse matrices; the interfaces to these routines are available in the module psb_util_mod.

hb_read — Read a sparse matrix from a file in the Harwell–Boeing format

call hb_read(a, iret, iunit, filename, b, mtitle)

Type: Asynchronous.

On Entry

filename The name of the file to be read.

Type:optional.

Specified as: a character variable containing a valid file name, or -, in which case the default input unit 5 (i.e. standard input in Unix jargon) is used. Default: -.

iunit The Fortran file unit number.

Type:optional.

Specified as: an integer value. Only meaningful if filename is not -.

On Return

a the sparse matrix read from file.

Type:required.

Specified as: a structured data of type psb_Tspmat_type.

b Rigth hand side(s).

Type: Optional

An array of type real or complex, rank 2 and having the ALLOCATABLE attribute; will be allocated and filled in if the input file contains a right hand side, otherwise will be left in the UNALLOCATED state.

mtitle Matrix title.

Type: Optional

A charachter variable of length 72 holding a copy of the matrix title as specified by the Harwell-Boeing format and contained in the input file.

iret Error code.

Type: required

hb_write — Write a sparse matrix to a file in the Harwell–Boeing format

call hb_write(a, iret, iunit, filename, key, rhs, mtitle)

Type: Asynchronous.

On Entry

a the sparse matrix to be written.

Type:required.

Specified as: a structured data of type psb_Tspmat_type.

b Rigth hand side.

 ${\bf Type:\ Optional}$

An array of type real or complex, rank 1 and having the ALLOCATABLE attribute; will be allocated and filled in if the input file contains a right hand side.

filename The name of the file to be written to.

Type:**optional**.

Specified as: a character variable containing a valid file name, or -, in which case the default output unit 6 (i.e. standard output in Unix jargon) is used. Default: -.

iunit The Fortran file unit number.

Type:optional.

Specified as: an integer value. Only meaningful if filename is not -.

key Matrix key.

Type: Optional

A charachter variable of length 8 holding the matrix key as specified by the Harwell-Boeing format and to be written to file.

mtitle Matrix title.

Type: Optional

A charachter variable of length 72 holding the matrix title as specified by the Harwell-Boeing format and to be written to file.

On Return

iret Error code.

Type: required

mm_mat_read — Read a sparse matrix from a file in the MatrixMarket format

call mm_mat_read(a, iret, iunit, filename)

Type: Asynchronous.

On Entry

filename The name of the file to be read.

Type:optional.

Specified as: a character variable containing a valid file name, or \neg , in which case the default input unit 5 (i.e. standard input in Unix jargon) is used. Default: \neg .

iunit The Fortran file unit number.

Type:optional.

Specified as: an integer value. Only meaningful if filename is not -.

On Return

a the sparse matrix read from file.

Type:required.

Specified as: a structured data of type psb_Tspmat_type.

iret Error code.

Type: required

mm_array_read — Read a dense array from a file in the MatrixMarket format

call mm_array_read(b, iret, iunit, filename)

Type: Asynchronous.

On Entry

filename The name of the file to be read.

Type:**optional**.

Specified as: a character variable containing a valid file name, or \neg , in which case the default input unit 5 (i.e. standard input in Unix jargon) is used. Default: \neg .

iunit The Fortran file unit number.

Type:optional.

Specified as: an integer value. Only meaningful if filename is not -.

On Return

b Rigth hand side(s).

Type: required

An array of type real or complex, rank 1 or 2 and having the ALLOCAT-ABLE attribute; will be allocated and filled in if the input file contains a right hand side, otherwise will be left in the UNALLOCATED state.

iret Error code.

Type: required

mm_mat_write — Write a sparse matrix to a file in the MatrixMarket format

call mm_mat_write(a, mtitle, iret, iunit, filename)

Type: Asynchronous.

On Entry

a the sparse matrix to be written.

Type:required.

Specified as: a structured data of type psb_Tspmat_type.

mtitle Matrix title.

Type: required

A charachter variable holding a descriptive title for the matrix to be written to file.

filename The name of the file to be written to.

Type:optional.

Specified as: a character variable containing a valid file name, or -, in which case the default output unit 6 (i.e. standard output in Unix jargon) is used. Default: -.

iunit The Fortran file unit number.

Type:optional.

Specified as: an integer value. Only meaningful if filename is not -.

On Return

iret Error code.

Type: required

mm_array_write — Write a dense array from a file in the MatrixMarket format

call mm_array_write(b, iret, iunit, filename)

Type: Asynchronous.

On Entry

b Rigth hand side(s).

 ${\bf Type:\ required}$

An array of type real or complex, rank 1 or 2; will be written..

filename The name of the file to be written.

Type:optional.

Specified as: a character variable containing a valid file name, or \neg , in which case the default input unit 5 (i.e. standard input in Unix jargon) is used. Default: \neg .

iunit The Fortran file unit number.

Type:optional.

Specified as: an integer value. Only meaningful if filename is not -.

On Return

iret Error code.

Type: required

10 Preconditioner routines

- Diagonal Scaling
- Block Jacobi with ILU(0) factorization

The supporting data type and subroutine interfaces are defined in the module psb_prec_mod. The old interfaces psb_precinit and psb_precbld are still supported for backward compatibility

init — Initialize a preconditioner

call prec%init(ptype, info)

Type: Asynchronous.

On Entry

ptype the type of preconditioner. Scope: global

Type: **required** Intent: **in**.

Specified as: a character string, see usage notes.

On Exit

prec Scope: local
Type: required
Intent: inout.

Specified as: a preconditioner data structure psb_prec_type.

info Scope: global
Type: required
Intent: out.

Error code: if no error, 0 is returned.

Notes Legal inputs to this subroutine are interpreted depending on the *ptype* string as follows⁴:

NONE No preconditioning, i.e. the preconditioner is just a copy operator.

- **DIAG** Diagonal scaling; each entry of the input vector is multiplied by the reciprocal of the sum of the absolute values of the coefficients in the corresponding row of matrix A;
- **BJAC** Precondition by a factorization of the block-diagonal of matrix A, where block boundaries are determined by the data allocation boundaries for each process; requires no communication. Only the incomplete factorization ILU(0) is currently implemented.

⁴The string is case-insensitive

build — Builds a preconditioner

call prec%build(a, desc_a, info[,amold,vmold,imold])

Type: Synchronous.

On Entry

a the system sparse matrix. Scope: local

Type: **required**Intent: **in**, target.

Specified as: a sparse matrix data structure psb_Tspmat_type.

prec the preconditioner.

Scope: **local**Type: **required**Intent: **inout**.

Specified as: an already initialized precondtioner data structure psb_prec_type

desc_a the problem communication descriptor. Scope: local

Type: **required**Intent: **in**, target.

Specified as: a communication descriptor data structure psb_desc_type.

 $\mathbf{a}\mathbf{m}\mathbf{o}\mathbf{l}\mathbf{d}$ The desired dynamic type for the internal matrix storage.

Scope: local. Type: optional. Intent: in.

Specified as: an object of a class derived from psb_T_base_sparse_mat.

vmold The desired dynamic type for the internal vector storage.

Scope: local. Type: optional. Intent: in.

Specified as: an object of a class derived from psb_T_base_vect_type.

imold The desired dynamic type for the internal integer vector storage.

Scope: local. Type: optional. Intent: in.

Specified as: an object of a class derived from (integer) psb_T_base_vect_type.

On Return

prec the preconditioner.

Scope: local
Type: required
Intent: inout.

Specified as: a precondtioner data structure psb_prec_type

info Error code.

Scope: local Type: required Intent: out.

An integer value; 0 means no error has been detected.

The <code>amold</code>, <code>vmold</code> and <code>imold</code> arguments may be employed to interface with special devices, such as GPUs and other accelerators.

apply — Preconditioner application routine

call prec%apply(x,y,desc_a,info,trans,work)
call prec%apply(x,desc_a,info,trans)

Type: Synchronous.

On Entry

prec the preconditioner. Scope: local

Type: **required** Intent: **in**.

Specified as: a preconditioner data structure psb_prec_type.

 \mathbf{x} the source vector. Scope: local

Type: required Intent: inout.

Specified as: a rank one array or an object of type psb_T_vect_type.

 $\mathbf{desc}_{-\mathbf{a}}$ the problem communication descriptor. Scope: \mathbf{local}

Type: required Intent: in.

Specified as: a communication data structure psb_desc_type.

trans Scope:

Type: **optional** Intent: **in**.

Specified as: a character.

work an optional work space Scope: local

Type: **optional** Intent: **inout**.

Specified as: a double precision array.

On Return

y the destination vector. Scope: local

Type: **required** Intent: **inout**.

Specified as: a rank one array or an object of type psb_T_vect_type.

info Error code.

Scope: local Type: required Intent: out.

descr — Prints a description of current preconditioner

```
call prec%descr()
call prec%descr(iout, root)
```

Type: Asynchronous.

On Entry

prec the preconditioner. Scope: local

 ${\bf Type:}\ {\bf required}$

Intent: in.

Specified as: a preconditioner data structure psb_prec_type.

iout output unit. Scope: local

Type: **optional** Intent: **in**.

Specified as: an integer number. Default: default output unit.

root Process from which to print Scope: local

Type: **optional** Intent: **in**.

Specified as: an integer number between 0 and np-1, in which case the specified process will print the description, or -1, in which case all

processes will print. Default: 0.

${\bf clone-clone}\ {\bf current\ preconditioner}$

call prec%clone(precout,info)

Type: Asynchronous.

On Entry

prec the preconditioner.

 ${\bf Scope:\ local.}$

On Return

precout A copy of the input object.

info Return code.

free — Free a preconditioner

call prec%free(info)

Type: Asynchronous.

On Entry

 ${\bf prec}\;$ the preconditioner.

Scope: local.
Type: required
Intent: inout.

Specified as: a preconditioner data structure psb_prec_type.

On Exit

prec Scope: local
 Type: required
 Intent: inout.

Specified as: a preconditioner data structure psb_prec_type.

info Scope: global
Type: required
Intent: out.

Error code: if no error, 0 is returned.

Notes Releases all internal storage.

11 Iterative Methods

In this chapter we provide routines for preconditioners and iterative methods. The interfaces for Krylov subspace methods are available in the module psb_krylov_mod.

psb_krylov — Krylov Methods Driver Routine

This subroutine is a driver that provides a general interface for all the Krylov-Subspace family methods implemented in PSBLAS version 2.

The stopping criterion can take the following values:

1 normwise backward error in the infinity norm; the iteration is stopped when

$$err = \frac{\|r_i\|}{(\|A\|\|x_i\| + \|b\|)} < eps$$

2 Relative residual in the 2-norm; the iteration is stopped when

$$err = \frac{\|r_i\|}{\|b\|_2} < eps$$

3 Relative residual reduction in the 2-norm; the iteration is stopped when

$$err = \frac{\|r_i\|}{\|r_0\|_2} < eps$$

The behaviour is controlled by the istop argument (see later). In the above formulae, x_i is the tentative solution and $r_i = b - Ax_i$ the corresponding residual at the *i*-th iteration.

Type: Synchronous.

On Entry

method a string that defines the iterative method to be used. Supported values are:

CG: the Conjugate Gradient method;

CGS: the Conjugate Gradient Stabilized method;

GCR: the Generalized Conjugate Residual method;

FCG: the Flexible Conjugate Gradient method⁵;

BICG: the Bi-Conjugate Gradient method;

BICGSTAB: the Bi-Conjugate Gradient Stabilized method;

BICGSTABL: the Bi-Conjugate Gradient Stabilized method with restarting:

RGMRES: the Generalized Minimal Residual method with restarting.

 \mathbf{a} the local portion of global sparse matrix A.

Scope: local
Type: required
Intent: in.

Specified as: a structured data of type psb_Tspmat_type.

⁵Note: the implementation is for FCG(1).

prec The data structure containing the preconditioner.

Scope: local
Type: required
Intent: in.

Specified as: a structured data of type psb_prec_type.

b The RHS vector.

Scope: local
Type: required
Intent: in.

Specified as: a rank one array or an object of type psb_T_vect_type.

 \mathbf{x} The initial guess.

Scope: local Type: required Intent: inout.

Specified as: a rank one array or an object of type psb_T_vect_type.

eps The stopping tolerance.

Scope: **global**Type: **required**Intent: **in**.

Specified as: a real number.

desc_a contains data structures for communications.

Scope: local
Type: required
Intent: in.

Specified as: a structured data of type psb_desc_type.

itmax The maximum number of iterations to perform.

Scope: **global**Type: **optional**Intent: **in**.

Default: itmax = 1000.

Specified as: an integer variable $itmax \ge 1$.

itrace If > 0 print out an informational message about convergence every itrace

iterations.
Scope: global
Type: optional
Intent: in.

irst An integer specifying the restart parameter.

Scope: **global**Type: **optional**.
Intent: **in**.

Values: irst > 0. This is employed for the BiCGSTABL or RGMRES

methods, otherwise it is ignored.

istop An integer specifying the stopping criterion.

 ${\bf Scope: \ global}$

Type: optional.

Intent: in.

Values: 1: use the normwise backward error, 2: use the scaled 2-norm of the residual, 3: use the residual reduction in the 2-norm. Default: 2.

On Return

 \mathbf{x} The computed solution.

Scope: **local**Type: **required**Intent: **inout**.

Specified as: a rank one array or an object of type psb_T_vect_type.

iter The number of iterations performed.

Scope: global Type: optional Intent: out.

Returned as: an integer variable.

err The convergence estimate on exit.

Scope: **global**Type: **optional**Intent: **out**.

Returned as: a real number.

cond An estimate of the condition number of matrix A; only available with the

CG method on real data.

Scope: **global**Type: **optional**Intent: **out**.

Returned as: a real number. A correct result will be greater than or equal to one; if specified for non-real data, or an error occurred, zero is returned.

info Error code.

Scope: local
Type: required
Intent: out.

References

- [1] D. Barbieri, V. Cardellini, S. Filippone and D. Rouson *Design Patterns* for Scientific Computations on Sparse Matrices, HPSS 2011, Algorithms and Programming Tools for Next-Generation High-Performance Scientific Software, Bordeaux, Sep. 2011
- [2] G. Bella, S. Filippone, A. De Maio and M. Testa, A Simulation Model for Forest Fires, in J. Dongarra, K. Madsen, J. Wasniewski, editors, Proceedings of PARA 04 Workshop on State of the Art in Scientific Computing, pp. 546–553, Lecture Notes in Computer Science, Springer, 2005.
- [3] A. Buttari, D. di Serafino, P. D'Ambra, S. Filippone, 2LEV-D2P4: a package of high-performance preconditioners, Applicable Algebra in Engineering, Communications and Computing, Volume 18, Number 3, May, 2007, pp. 223-239
- [4] P. D'Ambra, S. Filippone, D. Di Serafino On the Development of PSBLAS-based Parallel Two-level Schwarz Preconditioners Applied Numerical Mathematics, Elsevier Science, Volume 57, Issues 11-12, November-December 2007, Pages 1181-1196.
- [5] Dongarra, J. J., DuCroz, J., Hammarling, S. and Hanson, R., An Extended Set of Fortran Basic Linear Algebra Subprograms, ACM Trans. Math. Softw. vol. 14, 1–17, 1988.
- [6] Dongarra, J., DuCroz, J., Hammarling, S. and Duff, I., A Set of level 3 Basic Linear Algebra Subprograms, ACM Trans. Math. Softw. vol. 16, 1– 17, 1990.
- [7] J. J. Dongarra and R. C. Whaley, A User's Guide to the BLACS v. 1.1, Lapack Working Note 94, Tech. Rep. UT-CS-95-281, University of Tennessee, March 1995 (updated May 1997).
- [8] I. Duff, M. Marrone, G. Radicati and C. Vittoli, Level 3 Basic Linear Algebra Subprograms for Sparse Matrices: a User Level Interface, ACM Transactions on Mathematical Software, 23(3), pp. 379–401, 1997.
- [9] I. Duff, M. Heroux and R. Pozo, An Overview of the Sparse Basic Linear Algebra Subprograms: the New Standard from the BLAS Technical Forum, ACM Transactions on Mathematical Software, 28(2), pp. 239–267, 2002.
- [10] S. Filippone and M. Colajanni, PSBLAS: A Library for Parallel Linear Algebra Computation on Sparse Matrices, ACM Transactions on Mathematical Software, 26(4), pp. 527–550, 2000.
- [11] S. Filippone and A. Buttari, Object-Oriented Techniques for Sparse Matrix Computations in Fortran 2003, ACM Transactions on Mathematical Software, 38(4), 2012.
- [12] S. Filippone, P. D'Ambra, M. Colajanni, Using a Parallel Library of Sparse Linear Algebra in a Fluid Dynamics Applications Code on Linux Clusters, in G. Joubert, A. Murli, F. Peters, M. Vanneschi, editors, Parallel Computing - Advances & Current Issues, pp. 441–448, Imperial College Press, 2002.

- [13] Gamma, E., Helm, R., Johnson, R., and Vlissides, J. 1995. Design Patterns: Elements of Reusable Object-Oriented Software. Addison-Wesley.
- [14] Karypis, G. and Kumar, V., METIS: Unstructured Graph Partitioning and Sparse Matrix Ordering System. Minneapolis, MN 55455: University of Minnesota, Department of Computer Science, 1995. Internet Address: http://www.cs.umn.edu/~karypis.
- [15] Lawson, C., Hanson, R., Kincaid, D. and Krogh, F., Basic Linear Algebra Subprograms for Fortran usage, ACM Trans. Math. Softw. vol. 5, 38–329, 1979.
- [16] Machiels, L. and Deville, M. Fortran 90: An entry to object-oriented programming for the solution of partial differential equations. ACM Trans. Math. Softw. vol. 23, 32–49.
- [17] Metcalf, M., Reid, J. and Cohen, M. Fortran 95/2003 explained. Oxford University Press, 2004.
- [18] Rouson, D.W.I., Xia, J., Xu, X.: Scientific Software Design: The Object-Oriented Way. Cambridge University Press (2011)
- [19] M. Snir, S. Otto, S. Huss-Lederman, D. Walker and J. Dongarra, MPI: The Complete Reference. Volume 1 - The MPI Core, second edition, MIT Press, 1998.