

# PSBLAS-2.0 User's guide

---

*A reference guide for the Parallel Sparse BLAS  
library*

by **Salvatore Filippone**  
and **Alfredo Buttari**

“Tor Vergata” University of Rome. March 13, 2006

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>General overview</b>	<b>2</b>
<b>3</b>	<b>Data Structures</b>	<b>4</b>
3.1	Sparse Matrix data structure . . . . .	4
3.2	Descriptor data structure . . . . .	6
3.3	Preconditioner data structure . . . . .	8
<b>4</b>	<b>Algebraic routines</b>	<b>10</b>
	psb_geaxpby . . . . .	11
	psb_gedot . . . . .	14
	psb_gedot . . . . .	16
	psb_geamax . . . . .	18
	psb_geamax . . . . .	20
	psb_geasum . . . . .	22
	psb_genrm2 . . . . .	24
	psb_spnrmi . . . . .	26
	psb_spm . . . . .	28
	psb_spsm . . . . .	31
<b>5</b>	<b>Communication routines</b>	<b>35</b>
	psb_halo . . . . .	36
	psb_ovrl . . . . .	38
	psb_gather . . . . .	41
	psb_scatter . . . . .	44
<b>6</b>	<b>Data management and initialization routines</b>	<b>47</b>
	psb_geall . . . . .	48
	psb_geasb . . . . .	49
	psb_csrp . . . . .	50
	psb_cdprt . . . . .	51
	psb_gefree . . . . .	52
	psb_gelp . . . . .	53
	psb_spins . . . . .	54
	psb_cdall . . . . .	56
	psb_cdasb . . . . .	58
	psb_cdcpy . . . . .	59
	psb_cdfree . . . . .	60
	psb_cdins . . . . .	61

psb_cdren	63
psb_spall	64
psb_spassb	65
psb_spcnv	66
psb_spfree	67
psb_geins	68
psb_sprn	70
psb_glob_to_loc	71
psb_loc_to_glob	72
<b>7 Iterative Methods</b>	<b>73</b>
psb_cg	74
psb_cgs	77
psb_bicg	80
psb_bicgstab	83
psb_bicgstabl	86
psb_gmres	89
<b>8 Preconditioner routines</b>	<b>92</b>
psb_precset	93
psb_precbld	94
psb_precaply	95
<b>9 Error handling</b>	<b>97</b>
psb_errpush	100
psb_error	101
psb_set_errverbosity	102
psb_set_erraction	103
psb_errcomm	104

# 1 Introduction

The PSBLAS library, developed with the aim to facilitate the parallelization of computationally intensive scientific applications, is designed to address parallel implementation of iterative solvers for sparse linear systems through the distributed memory paradigm. It includes routines for multiplying sparse matrices by dense matrices, solving block diagonal systems with triangular diagonal entries, preprocessing sparse matrices, and contains additional routines for dense matrix operations. The current implementation of PSBLAS addresses a distributed memory execution model operating with message passing. However, the overall design does not preclude different implementation paradigms, such as those based on a shared memory model.

The PSBLAS library is internally implemented in a mixture of Fortran 77 and Fortran 95 [?] programming languages. A similar approach has been advocated by a number of authors, e.g. [?]. Moreover, the Fortran 95 facilities for dynamic memory management and interface overloading greatly enhance the usability of the PSBLAS subroutines. In this way, the library can take care of runtime memory requirements that are quite difficult or even impossible to predict at implementation or compilation time. The following presentation of the PSBLAS library follows the general structure of the proposal for serial Sparse BLAS [?], which in its turn is based on the proposal for BLAS on dense matrices [?, ?, ?].

The applicability of sparse iterative solvers to many different areas causes some terminology problems because the same concept may be denoted through different names depending on the application area. The PSBLAS features presented in this section will be discussed mainly in terms of finite difference discretizations of Partial Differential Equations (PDEs). However, the scope of the library is wider than that: for example, it can be applied to finite element discretizations of PDEs, and even to different classes of problems such as nonlinear optimization, for example in optimal control problems.

The design of a solver for sparse linear systems is driven by many conflicting objectives, such as limiting occupation of storage resources, exploiting regularities in the input data, exploiting hardware characteristics of the parallel platform. To achieve an optimal communication to computation ratio on distributed memory machines it is essential to keep the *data locality* as high as possible; this can be done through an appropriate data allocation strategy. The choice of the preconditioner is another very important factor that affects efficiency of the implemented application. Optimal data distribution requirements for a given preconditioner may conflict with distribution requirements of the rest of the solver. Finding the optimal trade-off may be very difficult because it is application dependent. Possible solution to these

problems and other important inputs to the development of the PSBLAS software package has come from an established experience in applying the PSBLAS solvers to computational fluid dynamics applications.

## 2 General overview

The PSBLAS library is designed to handle the implementation of iterative solvers for sparse linear systems on distributed memory parallel computers. The system coefficient matrix  $A$  must be square; it may be real or complex, nonsymmetric, and its sparsity pattern needs not to be symmetric. The serial computation parts are based on the serial sparse BLAS, so that any extension made to the data structures of the serial kernels is available to the parallel version. The overall design and parallelization strategy have been influenced by the structure of the ScaLAPACK parallel library [?]. The layered structure of the PSBLAS library is shown in figure 1 ; lower layers of the library indicate an encapsulation relationship with upper layers. The ongoing discussion focuses on the Fortran 95 layer immediately below the application layer. The serial parts of the computation on each process are executed through calls to the serial sparse BLAS subroutines. In a similar way, the inter-process message exchanges are implemented through the Basic Linear Algebra Communication Subroutines (BLACS) library [?] that guarantees a portable and efficient communication layer. The Message Passing Interface code is encapsulated within the BLACS layer. However, in some cases, MPI routines are directly used either to improve efficiency or to implement communication patterns for which the BLACS package doesn't provide any method.




Figure 1: PSBLAS library components hierarchy.

The PSBLAS library consists of two classes of subroutines that is, the

*computational routines* and the *auxiliary routines*. The computational routine set includes:

- Sparse matrix by dense matrix product;
- Sparse triangular systems solution for block diagonal matrices;
- Vector and matrix norms;
- Dense matrix sums;
- Dot products.

The auxiliary routine set includes:

- Communication descriptors allocation;
- Dense and sparse matrix allocation;
- Dense and sparse matrix build and update;
- Sparse matrix and data distribution preprocessing.

The following naming scheme has been adopted for all the symbols internally defined in the PSBLAS software package:

- all the symbols (i.e. subroutine names, data types...) are prefixed by `psb_`
- all the data type names are suffixed by `_type`
- all the constant values are suffixed by `_`
- all the subroutine names follow the rule `psb_xxname` where `xx` can be either:
  - `ge`: the routine is related to dense data,
  - `sp`: the routine is related to sparse data,
  - `cd`: the routine is related to communication descriptor (see 3).

For example the `psb_geins`, `psb_spins` and `psb_cdins` perform the same action (see 6) on dense matrices, sparse matrices and communication descriptors respectively. Interface overloading allows the usage of the same subroutine interfaces for both real and complex data.

## 3 Data Structures

In this chapter are illustrated data structures used for definition of routines interfaces. This include data structure for sparse matrix, communication descriptor and preconditioner. These data structures are used for calling PSBLAS routines in Fortran 90 language and will be used to next chapters containing these callings. Their definitions are included in the modules `psb_spmat_type`, `psb_descriptor_type` and `psb_prec_type`.

### 3.1 Sparse Matrix data structure

The `psb_spmat_type` data structure contains all information about local portion of the sparse matrix and its storage mode. Many of this fields are set in fully-transparent mode by PSBLAS-TOOLS routines when inserting a new sparse matrix, user must set only fields which describe matrix storage mode. Fields contained in Sparse matrix structures are:

- aspk** Contains values of the local distributed sparse matrix.  
Specified as: a pointer to an array of rank one of type corresponding to matrix entries type .
- ia1** Holds integer information on distributed sparse matrix. Actual information will depend on data format used.  
Specified as: a pointer to an integer array of rank one.
- ia2** Holds integer information on distributed sparse matrix. Actual information will depend on data format used.  
Specified as: a pointer to an integer array of rank one.
- infoa** On entry can hold auxiliary information on distributed sparse matrix. Actual information will depend on data format used.  
Specified as: integer array of length 10.
- fida** Defines the format of the distributed sparse matrix.  
Specified as: a string of length 5
- descra** Describe the characteristic of the distributed sparse matrix.  
Specified as: array of character of length 9.
- pl** Specifies the local row permutation of distributed sparse matrix. If `pl(1)` is equal to 0, then there isn't row permutation.  
Specified as: pointer to integer array of dimension equal to number of local row (`matrix_data[psb_n_row_]`)

- pr** Specifies the local column permutation of distributed sparse matrix. If  $PR(1)$  is equal to 0, then there isn't column permutation. Specified as: pointer to integer array of dimension equal to number of local row (`matrix_data[psb_n_col_]`)
- m** Number of rows; if row indices are stored explicitly, as in Coordinate Storage, should be greater than or equal to the maximum row index actually present in the sparse matrix. Specified as: integer variable.
- k** Number of columns; if column indices are stored explicitly, as in Coordinate Storage or Compressed Sparse Rows, should be greater than or equal to the maximum column index actually present in the sparse matrix. Specified as: integer variable.

FORTTRAN95 interface for distributed sparse matrices containing double precision real entries is defined as in figure 2.

```

type psb_dspmat_type
  integer      :: m, k
  character    :: fida(5)
  character    :: descra(10)
  integer      :: infoa(10)
  real(kind(1.d0)), pointer :: aspck(:)
  integer, pointer :: ia1(:), ia2(:), pr(:), pl(:)
end type psb_dspmat_type

```

Figure 2: The PSBLAS defined data type that contains a sparse matrix.

The following two cases are among the most commonly used:

**fida="CSR"** Compressed storage by rows. In this case the following should hold:

1.  $ia2(i)$  contains the index of the first element of row  $i$ ; the last element of the sparse matrix is thus stored at index  $ia2(m+1) - 1$ . It should contain  $m+1$  entries in nondecreasing order (strictly increasing, if there are no empty rows).
2.  $ia1(j)$  contains the column index and  $aspck(j)$  contains the corresponding coefficient value, for all  $ia2(1) \leq j \leq ia2(m+1) - 1$ .

**fida="COO"** Coordinate storage. In this case the following should hold:



1. `infoa(1)` contains the number of nonzero elements in the matrix;
2. For all  $1 \leq j \leq \text{infoa}(1)$ , the coefficient, row index and column index are stored into `apsk(j)`, `ia1(j)` and `ia2(j)` respectively.

### 3.2 Descriptor data structure

All the general matrix informations and elements to be exchanged among processes are stored within a data structure of the type `psb_desc_type`. Every structure of this type is associated to a sparse matrix, it contains data about general matrix informations and elements to be exchanged among processes.

It is not necessary for the user to know the internal structure of `psb_desc_type`, it is set in fully-transparent mode by PSBLAS-TOOLS routines when inserting a new sparse matrix, however the definition of the descriptor is the following.

**matrix\_data** includes general information about matrix and BLACS grid.

More precisely:

**matrix\_data[psb\_dec\_type\_]** Identifies the decomposition type (global); the actual values are internally defined, so they should never be accessed directly.

**matrix\_data[psb\_ctxt\_]** Communication context as returned by the BLACS (global).

**matrix\_data[psb\_m\_]** Total number of equations (global).

**matrix\_data[psb\_n\_]** Total number of variables (global).

**matrix\_data[psb\_n\_row\_]** Number of grid variables owned by the current process (local); equivalent to the number of local rows in the sparse coefficient matrix.

**matrix\_data[psb\_n\_col\_]** Total number of grid variables read by the current process (local); equivalent to the number of local columns in the sparse coefficient matrix. They include the halo.

Specified as: a pointer to integer array of dimension 10.

**halo\_index** A list of the halo and boundary elements for the current process to be exchanged with other processes; for each processes with which it is necessary to communicate:

1. Process identifier;

2. Number of points to be received;
3. Indices of points to be received;
4. Number of points to be sent;
5. Indices of points to be sent;

The list may contain an arbitrary number of groups; its end is marked by a -1.

Specified as: a pointer to an integer array of rank one.

**ovrlap\_index** A list of the overlap elements for the current process, organized in groups like the previous vector:

1. Process identifier;
2. Number of points to be received;
3. Indices of points to be received;
4. Number of points to be sent;
5. Indices of points to be sent;

The list may contain an arbitrary number of groups; its end is marked by a -1.

Specified as: a pointer to an integer array of rank one.

**ovrlap\_index** For all overlap points belonging to the current process:

1. Overlap point index;
2. Number of processes sharing that overlap points;

The list may contain an arbitrary number of groups; its end is marked by a -1.

Specified as: a pointer to an integer array of rank one.

**loc\_to\_glob** each element  $i$  of this array contains global identifier of the local variable  $i$ .

Specified as: a pointer to an integer array of rank one.

**glob\_to\_loc** if global variable  $i$  is read by current process then element  $i$  contains local index correspondent to global variable  $i$ ; else element  $i$  contains -1 (NULL) value.

Specified as: a pointer to an integer array of rank one.

FORTRAN95 interface for `psb_desc_type` structures is therefore defined as follows:

```

type psb_desc_type
  integer, pointer :: matrix_data(:), halo_index(:)
  integer, pointer :: overlap_elem(:), overlap_index(:)
  integer, pointer :: loc_to_glob(:), glob_to_loc(:)
end type psb_desc_type

```

Figure 3: The PSBLAS defined data type that contains the communication descriptor.

### 3.3 Preconditioner data structure

PSBLAS-2.0 offers the possibility to use many different types of preconditioning schemes. Besides the simple well known preconditioners like Diagonal Scaling or Block Jacobi (with ILU(0) incomplete factorization) also more complex preconditioning methods are implemented like the Additive Schwarz and Two-Level ones. A preconditioner is held in the `psb_prec_type` data structure which depends on the `psb_base_prec` reported in figure 4. The `psb_base_prec` data type may contain a simple preconditioning matrix with the associated communication descriptor which may be different than the system communication descriptor in the case of parallel preconditioners like the Additive Schwarz one. Then the `psb_prec_type` may contain more than one preconditioning matrix like in the case of Two-Level (in general Multi-Level) preconditioners. The user can choose the type of preconditioner to be used by means of the `psb_precset` subroutine; once the type of preconditioning method is specified, along with all the parameters that characterize it, the preconditioner data structure can be built using the `psb_precbuild` subroutine. This data structure wants to be flexible enough to easily allow the implementation of new kind of preconditioners. The values contained in the `iprcparm` and `dprcparm` define the type of preconditioner along with all the parameters related to it; thus, `iprcparm` and `dprcparm` define how the other records have to be interpreted.

```

type psb_base_prec

    type(psb_spmat_type), pointer    :: av(:) => null()
    real(kind(1.d0)), pointer       :: d(:)  => null()
    type(psb_desc_type), pointer    :: desc_data => null()
    integer, pointer                :: iprcparm(:) => null()
    real(kind(1.d0)), pointer       :: dprcparm(:) => null()
    integer, pointer                :: perm(:)  => null()
    integer, pointer                :: mlia(:)  => null()
    integer, pointer                :: invperm(:) => null()
    integer, pointer                :: nlaggr(:) => null()
    type(psb_spmat_type), pointer    :: aorig   => null()
    real(kind(1.d0)), pointer       :: dorig(:) => null()

end type psb_base_prec

type psb_prec_type
    type(psb_base_prec), pointer    :: baseprecv(:) => null()
    integer                        :: prec, base_prec
end type psb_prec_type

```

Figure 4: The PSBLAS defined data type that contains a preconditioner.

## 4 Algebraic routines

## psb\_geaxpby—General Dense Matrix Sum

This subroutine is an interface to the computational kernel for dense matrix sum:

$$y \leftarrow \alpha x + \beta y$$

where:

$x$  represents the global dense submatrix  $x_{:,jx:jx+n-1}$

$y$  represents the global dense submatrix  $y_{:,jy:jy+n-1}$

### Syntax

call psb\_geaxpby (*alpha*, *x*, *beta*, *y*, *desc\_a*, *info*)

call psb\_geaxpby (*alpha*, *x*, *beta*, *y*, *desc\_a*, *info*, *n*, *jx*, *jy*)

<i>x</i> , <i>y</i> , $\alpha$ , $\beta$	Subroutine
Single Precision Real	psb_geaxpby
Long Precision Real	psb_geaxpby
Long Precision Complex	psb_geaxpby

Table 1: Data types

### On Entry

**alpha** the scalar  $\alpha$ .

Scope: **global**

Type: **required**

Specified as: a number of the data type indicated in Table 1.

**x** the local portion of global dense matrix  $x$ .

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 1. The rank of  $x$  must be the same of  $y$ .

- beta** the scalar  $\beta$ .  
 Scope: **global**  
 Type: **required**  
 Specified as: a number of the data type indicated in Table 1.
- y** the local portion of the global dense matrix  $y$ .  
 Scope: **local**  
 Type: **required**  
 Specified as: a rank one or two array with the POINTER attribute containing numbers of the type indicated in Table 1. The rank of  $y$  must be the same of  $x$ .
- desc\_a** contains data structures for communications.  
 Scope: **local**  
 Type: **required**  
 Specified as: a structured data of type [psb\\_desc\\_type](#).
- n** number of columns in dense submatrices  $x$  and  $y$ .  
 Scope: **global**  
 Type: **optional**; can only be present if  $x$  and  $y$  are of rank 2.  
 Default: `min(size(x,2),size(y,2))`.  
 Specified as: an integer variable  $n \geq 0$ .
- jx** the column index of the global dense matrix  $x$ , identifying the first column of the submatrix  $x$ .  
 Scope: **global**  
 Type: **optional**; can only be present if  $x$  and  $y$  are of rank 2.  
 Default:  $jx = 1$ .  
 Specified as: an integer variable  $jx \geq 1$ .
- jy** the column index of the global dense matrix  $y$ , identifying the first column of the submatrix  $y$ .  
 Scope: **global**  
 Type: **optional**; can only be present if  $x$  and  $y$  are of rank 2.  
 Default:  $jy = 1$ .  
 Specified as: an integer variable  $jy \geq 1$ .

### On Return

- y** the local portion of result submatrix  $y$ .  
 Scope: **local**  
 Type: **required**  
 Specified as: a rank one or two array containing numbers of the type indicated in Table 1.

**info** the local portion of result submatrix  $y$ .  
Scope: **local**  
Type: **required**  
An integer value that contains an error code.



## psb\_gedot—Dot Product

This function computes dot product between two vectors  $x$  and  $y$ . If  $x$  and  $y$  are double precision real or single precision real vectors computes dot-product as:

$$dot \leftarrow x^T y$$

Else if  $x$  and  $y$  are double precision complex vectors then computes dot-product as:

$$dot \leftarrow x^H y$$

where:

$x$  represents the global subvector  $x_{:,jx}$

$y$  represents the global subvector  $y_{:,jy}$

## Syntax

`psb_gedot (x, y, desc_a, info)`

`psb_gedot (x, y, desc_a, info, jx, jy)`

<i>dot, x, y</i>	<b>Function</b>
Single Precision Real	psb_gedot
Long Precision Real	psb_gedot
Long Precision Complex	psb_gedot

Table 2: Data types

### On Entry

**x** the local portion of global dense matrix  $x$ . This function computes the location of the first element of local subarray used, based on  $jx$  and the field *matrix\_data* of *desc\_a*.

Scope: **local**

Type: **required**

Specified as: a pointer to array of rank one or two containing numbers of type specified in Table 2. The rank of  $x$  must be the same of  $y$ .

**y** the local portion of global dense matrix  $y$ . This function computes the location of the first element of local subarray used, based on  $iy, jy$  and the field *matrix\_data* of *desc\_a* .

Scope: **local**

Type: **required**

Specified as: a pointer to array of rank one or two containing numbers of type specified in Table 2. The rank of  $y$  must be the same of  $x$ .

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_desc_type`.

**jx** the column index of global dense matrix  $x$ , identifying the column of subvector  $x$ .

Scope: **global**

Type: **optional**; can only be present if  $x$  and  $y$  are of rank 2.

Default:  $jx = 1$ .

**jy** the column index of global dense matrix  $y$ , identifying the column of subvector  $y$ .

Scope: **global**

Type: **optional**; can only be present if  $x$  and  $y$  are of rank 2.

Default:  $jy = 1$ .

Specified as: an integer variable  $jy \geq 1$ .

## On Return

**Function value** is the dot product of subvectors  $x$  and  $y$ .

Scope: **global**

Specified as: a number of the data type indicated in Table 2.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## psb\_gedot—Generalized Dot Product

This subroutine computes a series of dot products among the columns of two dense matrices  $x$  and  $y$ :

$$res(i) \leftarrow x(:, i)^T y(:, i)$$

If the matrices are complex, then the usual convention applies, i.e. the conjugate transpose of  $x$  is used. If  $x$  and  $y$  are of rank one, then  $res$  is a scalar, else it is a rank one array.

### Syntax

psb\_gedot ( $res, x, y, desc\_a, info$ )

$res, x, y$	Subroutine
Single Precision Real	psb_gedot
Long Precision Real	psb_gedot
Long Precision Complex	psb_gedot

Table 3: Data types

### On Entry

**x** the local portion of global dense matrix  $x$ .

Scope: **local**

Type: **required**

Specified as: a pointer to array of rank one or two containing numbers of type specified in Table 3. The rank of  $x$  must be the same of  $y$ .

**y** the local portion of global dense matrix  $y$ .

Scope: **local**

Type: **required**

Specified as: a pointer to array of rank one or two containing numbers of type specified in Table 3. The rank of  $y$  must be the same of  $x$ .

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

### On Return

**res** is the dot product of subvectors  $x$  and  $y$ .

Scope: **global**

Specified as: a number or a rank-one array of the data type indicated in Table 2.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## psb\_geamax—Infinity-Norm of Vector

This function computes the infinity-norm of a vector  $x$ .

If  $x$  is double precision real or single precision real vector computes infinity norm as:

$$amax \leftarrow \max_i |x_i|$$

else if  $x$  is double precision complex vector then computes infinity-norm as:

$$amax \leftarrow \max_i (|re(x_i)| + |im(x_i)|)$$

where:

$x$  represents the global subvector  $x_{:,jx}$

## Syntax

`psb_geamax (x, desc_a, info)`

`psb_geamax (x, desc_a, info, jx)`

<i>amax</i>	<i>x</i>	<b>Function</b>
Single Precision Real	Single Precision Real	psb_geamax
Long Precision Real	Long Precision Real	psb_geamax
Long Precision Real	Long Precision Complex	psb_geamax

Table 4: Data types

## On Entry

**x** the local portion of global dense matrix  $x$ . This function computes the location of the first element of local subarray used, based on  $jx$  and the field *matrix\_data* of *desc\_a*.

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 4.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**jx** the column index of global dense matrix  $x$ , identifying the column of subvector  $x$ .

Scope: **global**

Type: **optional**; can only be present if  $x$  is of rank 2.

Default:  $jx = 1$

Specified as: an integer variable  $jx \geq 1$ .

### On Return

**Function value** is the infinity norm of subvector  $x$ .

Scope: **global**

Specified as: a number of the data type indicated in [Table 4](#).

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## psb\_geamax—Generalized Infinity Norm

This subroutine computes a series of infinity norms on the columns of a dense matrix  $x$ :

$$res(i) \leftarrow \max_k |x(k, i)|$$

### Syntax

psb\_geamax (*res*, *x*, *desc\_a*, *info*)

<i>res</i>	<i>x</i>	Subroutine
Single Precision Real	Single Precision Real	psb_geamax
Long Precision Real	Long Precision Real	psb_geamax
Long Precision Real	Long Precision Complex	psb_geamax

Table 5: Data types

### On Entry

**x** the local portion of global dense matrix  $x$ .

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 5.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

### On Return

**res** is the infinity norm of the columns of  $x$ .

Scope: **global**

Specified as: a number or a rank-one array of the data type indicated in Table 4.

**info** the local portion of result submatrix  $y$ .  
Scope: **local**  
Type: **required**  
An integer value that contains an error code.



## psb\_geasum—1-Norm of Vector

This function computes the 1-norm of a vector  $x$ .

If  $x$  is double precision real or single precision real vector computes 1-norm as:

$$asum \leftarrow \|x_i\|$$

else if  $x$  is double precision complex vector then computes 1-norm as:

$$asum \leftarrow \|re(x)\|_1 + \|im(x)\|_1$$

where:

$x$  represents the global subvector  $x_{:,jx}$

## Syntax

`psb_geasum (x, desc_a, info)`

`psb_geasum (x, desc_a, info, jx)`

<i>dot, x, y</i>	<b>Function</b>
Single Precision Real	<code>psb_geasum</code>
Long Precision Real	<code>psb_geasum</code>
Long Precision Complex	<code>psb_geasum</code>

Table 6: Data types

## On Entry

**x** the local portion of global dense matrix  $x$ . This function computes the location of the first element of local subarray used, based on  $jx$  and the field `matrix_data` of `desc_a`.

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 6.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**jx** the column index of global dense matrix  $x$ , identifying the column of subvector  $x$ .

Scope: **global**

Type: **optional**; can only be present if  $x$  is of rank 2.

Default:  $jx = 1$

Specified as: an integer variable  $jx \geq 1$ .

### On Return

**Function value** is the 1-norm of subvector  $x$ .

Scope: **global**

Specified as: a number of the data type indicated in [Table 6](#).

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## psb\_genrm2—2-Norm of Vector

This function computes the 2-norm of a vector  $x$ .

If  $x$  is double precision real or single precision real vector computes 2-norm as:

$$nrm2 \leftarrow \sqrt{x^T x}$$

else if  $x$  is double precision complex vector then computes 2-norm as:

$$nrm2 \leftarrow \sqrt{x^H x}$$

where:

$x$  represents the global subvector  $x_{:,jx}$

$nrm2, x$	Function
Single Precision Real	psb_genrm2
Long Precision Real	psb_genrm2
Long Precision Complex	psb_genrm2

Table 7: Data types

## Syntax

`psb_genrm2 (x, desc_a, info)`

`psb_genrm2 (x, desc_a, info, jx)`

### On Entry

**x** the local portion of global dense matrix  $x$ . This function computes the location of the first element of local subarray used, based on  $jx$  and the field `matrix_data` of `desc_a`.

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 7.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**jx** the column index of global dense matrix  $x$ , identifying the column of subvector  $x$ .

Scope: **global**

Type: **optional**; can only be present if  $x$  is of rank 2.

Default:  $jx = 1$

Specified as: an integer variable  $jx \geq 1$ .

### On Return

**Function Value** is the 2-norm of subvector  $x$ .

Scope: **global**

Type: **required**

Specified as: a number of the data type indicated in [Table 7](#).

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## psb\_spnrmi—Infinity Norm of Sparse Matrix

This function computes the infinity-norm of a matrix  $A$ :

$$nrmi \leftarrow \|A\|_{\infty}$$

where:

$A$  represents the global matrix  $A$

$nrmi, A$	Function
Single Precision Real	psb_spnrmi
Long Precision Real	psb_spnrmi
Long Precision Complex	psb_spnrmi

Table 8: Data types

### Syntax

`psb_spnrmi (A, desc_a, info)`

#### On Entry

**a** the local portion of the global sparse matrix  $A$ .

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_spmat\\_type](#).

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

#### On Return

**Function value** is the infinity-norm of sparse submatrix  $A$ .

Scope: **global**

Specified as: a number of the data type indicated in Table 8.

**info** the local portion of result submatrix  $y$ .  
Scope: **local**  
Type: **required**  
An integer value that contains an error code.

## psb\_spmmm—Sparse Matrix by Dense Matrix Product

This subroutine computes the Sparse Matrix by Dense Matrix Product:

$$y \leftarrow \alpha P_r A P_c x + \beta y \quad (1)$$

$$y \leftarrow \alpha P_r A^T P_c x + \beta y \quad (2)$$

$$y \leftarrow \alpha P_r A^H P_c x + \beta y \quad (3)$$

where:

$x$  is the global dense submatrix  $x_{:,jx:jx+k-1}$

$y$  is the global dense submatrix  $y_{:,jy:jy+k-1}$

$A$  is the global sparse submatrix  $A$

$P_r, P_c$  are the permutation matrices.

$A, x, y, \alpha, \beta$	Subroutine
Single Precision Real	psb_spmmm
Long Precision Real	psb_spmmm
Long Precision Complex	psb_spmmm

Table 9: Data types

## Syntax

CALL psb\_spmmm (*alpha, a, x, beta, y, desc\_a, info*)

CALL psb\_spmmm (*alpha, a, x, beta, y, desc\_a, info, trans, k, jx, jy, work*)

### On Entry

**alpha** the scalar  $\alpha$ .

Scope: **global**

Type: **required**

Specified as: a number of the data type indicated in Table 9.

- a** the local portion of the sparse matrix  $A$ .  
 Scope: **local**  
 Type: **required**  
 Specified as: a structured data of type [psb\\_spmat\\_type](#).
- x** the local portion of global dense matrix  $x$ . This subroutine computes the location of the first element of local subarray used, based on  $jx$  and the field *matrix\_data* of *desc\_a* .  
 Scope: **local**  
 Type: **required**  
 Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 9. The rank of  $x$  must be the same of  $y$ .
- beta** the scalar  $\beta$ .  
 Scope: **global**  
 Type: **required**  
 Specified as: a number of the data type indicated in Table 9.
- y** the local portion of global dense matrix  $y$ . This subroutine computes the location of the first element of local subarray used, based on  $jy$  and the field *matrix\_data* of *desc\_a* .  
 Scope: **local**  
 Type: **required**  
 Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 9. The rank of  $y$  must be the same of  $x$ .
- desc\_a** contains data structures for communications.  
 Scope: **local**  
 Type: **required**  
 Specified as: a structured data of type [psb\\_desc\\_type](#).
- trans** indicate what kind of operation to perform.
- trans** = **N** the operation is specified by equation 1  
**trans** = **T** the operation is specified by equation 2  
**trans** = **C** the operation is specified by equation 3
- Scope: **global**  
 Type: **optional**  
 Default: *trans* =  $N$   
 Specified as: a character variable.



**k** number of columns in dense submatrices  $x$  and  $y$ .

Scope: **global**

Type: **optional**

Default:  $\min(\text{size}(x,2)-jx+1, \text{size}(y,2)-jy+1)$

Specified as: an integer variable  $k \geq 1$ .

**jx** the column index of global dense matrix  $x$ , identifying the column of subvector  $x$ .

Scope: **global**

Type: **optional**; can only be present if  $x$  is of rank 2.

Default:  $iy = 1$

Specified as: an integer variable  $jx \geq 1$ .

**jy** the column index of global dense matrix  $y$ , identifying the column of subvector  $y$ .

Scope: **global**

Type: **optional**; can only be present if  $y$  is of rank 2.

Default:  $jy = 1$

Specified as: an integer variable  $jy \geq 1$ .

**work** the work array.

Scope: **local**

Specified as: a rank one array of the same type of  $x$  and  $y$  with the POINTER attribute.

### On Return

**y** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

Specified as: a pointer to array of rank one or two containing numbers of type specified in Table 9.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## psb\_spsm—Triangular System Solve

This subroutine computes the Triangular System Solve:

$$\begin{aligned}y &\leftarrow \alpha P_r T^{-1} P_c x + \beta y \\y &\leftarrow \alpha D P_r T^{-1} P_c x + \beta y \\y &\leftarrow \alpha P_r T^{-1} P_c D x + \beta y \\y &\leftarrow \alpha P_r T^{-T} P_c x + \beta y \\y &\leftarrow \alpha D P_r T^{-T} P_c x + \beta y \\y &\leftarrow \alpha P_r T^{-T} P_c D x + \beta y \\y &\leftarrow \alpha P_r T^{-H} P_c x + \beta y \\y &\leftarrow \alpha D P_r T^{-H} P_c x + \beta y \\y &\leftarrow \alpha P_r T^{-H} P_c D x + \beta y\end{aligned}$$

where:

$x$  is the global dense submatrix  $x_{:,jx:jx+n-1}$

$y$  is the global dense submatrix  $y_{:,jy:jy+n-1}$

$T$  is the global sparse block triangular submatrix  $T$

$D$  is the scaling diagonal matrix.

$P_r, P_c$  are the permutation matrices.

### Syntax

CALL psb\_spsm (*alpha, t, x, beta, y, desc\_a, info*)

CALL psb\_spsm

(*alpha, t, x, beta, y, desc\_a, info, trans, unit, choice, diag, n, jx, jy, work*)

### On Entry

$T, x, y, D, \alpha, \beta$	Subroutine
Single Precision Real	psb_spsm
Long Precision Real	psb_spsm
Long Precision Complex	psb_spsm

Table 10: Data types

**alpha** the scalar  $\alpha$ .

Scope: **global**

Type: **required**

Specified as: a number of the data type indicated in Table 10.

**t** the global portion of the sparse matrix  $T$ .

Scope: **local**

Type: **required**

Specified as: a structured data type specified in § 3.

**x** the local portion of global dense matrix  $x$ . This subroutine computes the location of the first element of local subarray used, based on  $jx$  and the field *matrix\_data* of *desc\_a*.

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 10. The rank of  $x$  must be the same of  $y$ .

**beta** the scalar  $\beta$ .

Scope: **global**

Type: **required**

Specified as: a number of the data type indicated in Table 10.

**y** the local portion of global dense matrix  $y$ . This subroutine computes the location of the first element of local subarray used, based on  $jy$  and the field *matrix\_data* of *desc\_a*.

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 10. The rank of  $y$  must be the same of  $x$ .

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**trans** specify with *unitd* the operation to perform.

**trans** = 'N' the operation is with no transposed matrix

**trans** = 'T' the operation is with transposed matrix.

**trans** = 'C' the operation is with conjugate transposed matrix.

Scope: **global**

Type: **optional**

Default: *trans* = N

Specified as: a character variable.

**unitd** specify with *trans* the operation to perform.

**unitd** = 'U' the operation is with no scaling

**unitd** = 'L' the operation is with left scaling

**unitd** = 'R' the operation is with right scaling.

Scope: **global**

Type: **optional**

Default: *unitd* = U

Specified as: a character variable.

**choice** specify whether a cleanup of the overlapped elements is required on exit.

**choice** = **.false.** no cleanup on exit

**choice** = **.true.** cleanup on exit.

Scope: **global**

Type: **optional**

Default: *choice* = *.true.*

Specified as: a logical variable.

**diag** the diagonal scaling matrix.

Scope: **local**

Type: **optional**

Default: *diag*(1) = 1(*noscaling*)

Specified as: a rank one array containing numbers of the type indicated in Table 10.

**n** number of columns in dense submatrices  $x$  and  $y$ .

Scope: **global**

Type: **optional**

Default:  $\min(\text{size}(x,2)-jx+1, \text{size}(y,2)-jy+1)$

Specified as: an integer variable  $n \geq 0$ .

**jx** the column index of global dense matrix  $x$ , identifying the column of subvector  $x$ .

Scope: **global**

Type: **optional**; can only be present if  $x$  is of rank 2.

Default:  $jx = 1$

Specified as: an integer variable  $jx \geq 1$ .

**jy** the column index of global dense matrix  $y$ , identifying the column of subvector  $y$ .

Scope: **global**

Type: **optional**; can only be present if  $y$  is of rank 2.

Default:  $jy = 1$

Specified as: an integer variable  $jy \geq 1$ .

Scope: **global**

Specified as: a number of the data type indicated in Table 10.

**work** the work array.

Scope: **local**

Type: **optional**

Specified as: a rank one array of the same type of  $x$  with the POINTER attribute.

### On Return

**y** the local portion of global dense matrix  $y$ . This subroutine computes the location of the first element of local subarray used, based on  $jy$  and the field *matrix\_data* of *desc\_a*.

Scope: **local**

Type: **required**

Specified as: a pointer to array of rank one or two containing numbers of type specified in Table 10.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## 5 Communication routines

## psb\_halo—Halo Data Communication

These subroutines restore a consistent status for the halo elements, and (optionally) scale the result:

$$x \leftarrow \alpha x$$

where:

$x$  is a global dense submatrix.

$\alpha, x$	Subroutine
Single Precision Real	psb_halo
Long Precision Real	psb_halo
Long Precision Complex	psb_halo

Table 11: Data types

## Syntax

CALL psb\_halo ( $x, desc\_a, info$ )

CALL psb\_halo ( $x, desc\_a, info, alpha, work$ )

### On Entry

**x** global dense matrix  $x$ .

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 11.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**alpha** the scalar  $\alpha$ .

Scope: **global**

Type: **optional**

Default:  $\alpha = 1$

Specified as: a number of the data type indicated in Table 11.

**work** the work array.

Scope: **local**

Type: **optional**

Specified as: a rank one array of the same type of  $x$  with the POINTER attribute.

### On Return

**x** global dense result matrix  $x$ .

Scope: **local**

Type: **required**

Returned as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 11.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.



## psb\_ovrl—Overlap Update

These subroutines restore a consistent status for the overlap elements:

$$x \leftarrow Qx$$

where:

$x$  is the global dense submatrix  $x$

$Q$  is the overlap operator; it is the composition of two operators  $P_a$  and  $P^T$ .

$x$	Subroutine
Single Precision Real	psb_ovrl
Long Precision Real	psb_ovrl
Long Precision Complex	psb_ovrl

Table 12: Data types

## Syntax

CALL psb\_ovrl ( $x$ ,  $desc\_a$ ,  $info$ )

CALL psb\_ovrl

( $x$ ,  $desc\_a$ ,  $info$ ,  $choice=choice$ ,  $update\_type=update\_type$ ,  $work=work$ )

### On Entry

**x** global dense matrix  $x$ .

Scope: **local**

Type: **required**

Specified as: a rank one or two array with the POINTER attribute containing numbers of type specified in Table 12.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**choice** specify if exchange overlap elements.

**choice** = **.true.** exchange overlap elements, i.e. apply operator  $P^T$ ;

**choice** = **.false.** don't exchange overlap elements

Scope: **global**

Type: **optional**

Default: *choice* = *.true.*

Specified as: a logical variable.

**update\_type** = **1** normal update  $P_a$ ;

**update\_type** = **2** square root update  $\sqrt{P_a}$ ;

Scope: **global**

Default: *update\_type* = *.true.*

Scope: **global**

Specified as: a integer variable.

**work** the work array.

Scope: **local**

Type: **optional**

Specified as: a one dimensional array of the same type of  $x$ .

## On Return

**x** global dense result matrix  $x$ .

Scope: **local**

Type: **required**

Specified as: a pointer to array of rank one or two containing numbers of type specified in Table 12.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## Usage notes

1. If there is no overlap in the data distribution, no operations are performed;

2. The operator  $P^T$  performs the reduction sum of overlap elements; it is the inverse of a “stretch” operator  $P$  that replicates overlap elements, accounting for the physical replication of data;
3. The operator  $P_a$  performs a scaling on the overlap elements by the amount of replication; thus, when combined with the reduction operator, it implements the average of replicated elements over all of their instances.
4. The square root update option makes it possible to apply the following operator:

$$x \leftarrow \sqrt{P_a} P^T K^{-1} P \sqrt{P_a} x$$

In the case of a symmetric  $K$ , this preserves symmetry of the overall preconditioner, which would otherwise be destroyed.

## psb\_gather—Gather Global Dense Matrix

These subroutines collect the portions of global dense matrix distributed over all process into one single array stored on one process.

$$glob\_x \leftarrow collect(loc\_x_i)$$

where:

$glob\_x$  is the global submatrix  $glob\_x_{iy:iy+m-1, jy:jy+n-1}$

$loc\_x_i$  is the local portion of global dense matrix on process  $i$ .

$collect$  is the collect function.

$x_i, y$	Subroutine
Single Precision Real	psb_gather
Long Precision Real	psb_gather
Long Precision Complex	psb_gather

Table 13: Data types

## Syntax

call psb\_gather

$(glob\_x, loc\_x, desc\_a, info, root, iglobx, jglobx, ilocx, jlocx, k)$

## Syntax

call psb\_gather  $(glob\_x, loc\_x, desc\_a, info, root, iglobx, ilocx)$

## On Entry

**loc\_x** the local portion of global dense matrix  $glob\_x$ .

Scope: **local**

Type: **required**

Specified as: a rank one or two array containing numbers of the type indicated in Table 13.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_desc_type`.

**root** The process that holds the global copy. If  $root = -1$  all the processes will have a copy of the global vector.

Scope: **global**

Type: **optional**

Specified as: an integer variable  $0 \leq ix \leq np$ .

**iglobx** Row index to define a submatrix in `glob_x` into which gather the local pieces.

Scope: **global**

Type: **optional**

Specified as: an integer variable  $1 \leq ix \leq matrix\_data(psb\_m\_)$ .

**jglobx** Column index to define a submatrix in `glob_x` into which gather the local pieces.

Scope: **global**

Type: **optional**

Specified as: an integer variable.

**ilocx** Row index to define a submatrix in `loc_x` that has to be gathered into `glob_x`.

Scope: **local**

Type: **optional**

Specified as: an integer variable.

**jlocx** Columns index to define a submatrix in `loc_x` that has to be gathered into `glob_x`.

Scope: **global**

Type: **optional**

Specified as: an integer variable.

**k** The number of columns to gather.

Scope: **global**

Type: **optional**

Specified as: an integer variable.

## On Return

**glob\_x** The array where the local parts must be gathered.

Scope: **global**

Type: **required**

Specified as: a rank one or two array.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## psb\_scatter—Scatter Global Dense Matrix

These subroutines scatters the portions of global dense matrix owned by a process to all the processes in the processes grid.

$$loc\_x_i \leftarrow scatter(lob\_x_i)$$

where:

$lob\_x$  is the global submatrix  $lob\_x_{iy:iy+m-1, jy:jy+n-1}$

$loc\_x_i$  is the local portion of global dense matrix on process  $i$ .

$scatter$  is the scatter function.

$x_i, y$	Subroutine
Single Precision Real	psb_scatter
Long Precision Real	psb_scatter
Long Precision Complex	psb_scatter

Table 14: Data types

## Syntax

call psb\_scatter

$(lob\_x, loc\_x, desc\_a, info, root, iglobx, jglobx, ilocx, jlocx, k)$

## Syntax

call psb\_scatter  $(lob\_x, loc\_x, desc\_a, info, root, iglobx, ilocx)$

## On Entry

**glob\_x** The array that must be scattered into local pieces.

Scope: **global**

Type: **required**

Specified as: a rank one or two array.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**root** The process that holds the global copy. If  $root = -1$  all the processes have a copy of the global vector.

Scope: **global**

Type: **optional**

Specified as: an integer variable  $0 \leq ix \leq np$ .

**iglobx** Row index to define a submatrix in `glob_x` that has to be scattered into local pieces.

Scope: **global**

Type: **optional**

Specified as: an integer variable  $1 \leq ix \leq matrix\_data(psb\_m\_)$ .

**jglobx** Column index to define a submatrix in `glob_x` that has to be scattered into local pieces.

Scope: **global**

Type: **optional**

Specified as: an integer variable.

**ilocx** Row index to define a submatrix in `loc_x` into which scatter the local piece of `glob_x`.

Scope: **local**

Type: **optional**

Specified as: an integer variable.

**jlocx** Columns index to define a submatrix in `loc_x` into which scatter the local piece of `glob_x`.

Scope: **global**

Type: **optional**

Specified as: an integer variable.

**k** The number of columns to scatter.

Scope: **global**

Type: **optional**

Specified as: an integer variable.

## On Return

**loc\_x** the local portion of global dense matrix `glob_x`.

Scope: **local**



Type: **required**

Specified as: a rank one or two array containing numbers of the type indicated in Table 14.

**info** the local portion of result submatrix  $y$ .

Scope: **local**

Type: **required**

An integer value that contains an error code.

## 6 Data management and initialization routines

## psb\_geall—Allocates a dense matrix

### Syntax

call psb\_geall (*m*, *n*, *x*, *desc\_a*, *info*, *js*)

#### On Entry

**m** The number of rows of the dense matrix to be allocated.

Scope: **local**

Type: **required**

Specified as: Integer scalar.

**n** The number of columns of the dense matrix to be allocated.

Scope: **local**

Type: **required**

Specified as: Integer scalar.

**desc\_a** The communication descriptor.

Scope: **local**

Type: **required**

Specified as: a variable of type [psb\\_desc\\_type](#).

**js** The starting column.

Scope: **local**

Type: **optional**

Specified as: Integer scalar.

#### On Return

**x** The dense matrix to be allocated.

Scope: **local**

Type: **required**

Specified as: a one or two dimensional array.

**info** Error code. Scope: **local**

Type: **required**

Specified as: Integer scalar.

## psb\_geasb—Assembly a dense matrix

### Syntax

```
call psb_geasb (x, desc_a, info)
```

### On Entry

**desc\_a** The communication descriptor.

Scope: **local**

Type: **required**

Specified as: a variable of type [psb\\_desc\\_type](#).

### On Return

**x** The dense matrix to be assembled.

Scope: **local**

Type: **required**

Specified as: a one or two dimensional array.

**info** Error code.

Scope: **local**

Type: **required**

Specified as: Integer scalar.

## **psb\_csrp**—Applies a right permutation to a sparse matrix

### **Syntax**

call `psb_csrp (trans, iperm, a, desc_a, info)`

### **On Entry**

**trans** A character that specifies whether to permute  $A$  or  $A^T$ .

Scope: **local**

Type: **required**

Specified as: a single character with value 'N' for  $A$  or 'T' for  $A^T$ .

**iperm** An integer array containing permutation information.

Scope: **local**

Type: **required**

Specified as: an integer one-dimensional array.

**a** The sparse matrix to be permuted.

Scope: **local**

Type: **required**

Specified as: a `psb_spmat_type` variable.

**desc\_a** The communication descriptor of type `psb_desc_type`.

Scope: **local**

Type: **required**

Specified as: a variable of type `psb_desc_type`.

### **On Return**

**info** Error code.

Scope: **local**

Type: **required**

Specified as: Integer scalar.

## psb\_cdprt—Prints a descriptor

### Syntax

call psb\_cdprt (*iout*, *desc\_a*, *glob*, *short*)

### On Entry

**iout** An integer that defines the output unit. Scope: **local**

Type: **required**

Specified as: Integer scalar.

**desc\_a** The communication descriptor of type [psb\\_desc.type](#) that must be printed.

Scope: **local**

Type: **required**

Specified as: a variable of type [psb\\_desc.type](#).

### On Return

**glob** ??????

**short** ??????

## psb\_gefree—Frees a dense matrix

### Syntax

call `psb_gefree (x, desc_a, info)`

### On Entry

**x** The dense matrix to be freed.

Scope: **local**

Type: **required**

Specified as: a one or two dimensional array.

**desc\_a** The communication descriptor.

Scope: **local**

Type: **required**

Specified as: a variable of type [psb\\_desc\\_type](#).

### On Return

**info** Error code.

Scope: **local**

Type: **required**

Specified as: Integer scalar.

## **psb\_gelp**—Applies a left permutation to a dense matrix

### Syntax

call `psb_gelp` (*trans*, *iperm*, *x*, *desc\_a*, *info*)

### On Entry

**trans** A character that specifies whether to permute  $A$  or  $A^T$ .

Scope: **local**

Type: **required**

Specified as: a single character with value 'N' for  $A$  or 'T' for  $A^T$ .

**iperm** An integer array containing permutation information.

Scope: **local**

Type: **required**

Specified as: an integer one-dimensional array.

**x** The dense matrix to be permuted.

Scope: **local**

Type: **required**

Specified as: a one or two dimensional array.

**desc\_a** The communication descriptor.

Scope: **local**

Type: **required**

Specified as: a variable of type [psb\\_desc\\_type](#).

### On Return

**info** Error code.

Scope: **local**

Type: **required**

Specified as: Integer scalar.



## psb\_spins—Insert a cloud of elements into a sparse matrix

### Syntax

call psb\_spins (*nz*, *ia*, *ja*, *val*, *a*, *desc\_a*, *info*, *is*, *js*)

### On Entry

**nz** the number of elements to be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer scalar.

**ia** the row indices of the elements to be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer array of size *nz*.

**ja** the column indices of the elements to be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer array of size *nz*.

**val** the elements to be inserted.

Scope:**local**.

Type:**required**.

Specified as: an array of size *nz*.

**desc\_a** The communication descriptor.

Scope: **local**.

Type: **required**.

Specified as: a variable of type [psb\\_desc\\_type](#).

**is** the starting row on matrix *a*.

Scope:**local**.

Type:**optional**.

Specified as: an integer vaule.

**js** the starting column on matrix *a*.

Scope:**local**.

Type:**optional**

Specified as: an integer value

### **On Return**

**a** the matrix into which elements will be inserted.

Scope:**local**

Type:**required**

Specified as: a structured data of type [psb\\_spmat\\_type](#).

**info** Error code.

Scope: **local**

Type: **required**

## psb\_cdall—Allocates a communication descriptor

### Syntax

call psb\_cdall (*m*, *n*, *parts*, *icontxt*, *desc\_a*, *info*)

call psb\_cdall (*m*, *v*, *icontxt*, *desc\_a*, *info*, *flag*)

### On Entry

**m** the number of rows of the problem.

Scope:**global**.

Type:**required**.

Specified as: an integer value.

**n** the number of columns of the problem.

Scope:**global**.

Type:**required**.

Specified as: an integer value.

**parts** the subroutine that defines the partitioning scheme.

Scope:**global**.

Type:**required**.

Specified as: a subroutine as described in ???

**icontxt** the communication context.

Scope:**global**.

Type:**required**.

Specified as: an integer value.

### On Return

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

**info** Error code. Scope: **local**  
Type: **required**  
Specified as: an integer variable.

## psb\_cdasb—Communication descriptor assembly routine

### Syntax

```
call psb_cdasb (desc_a, info)
```

### On Entry

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

### On Return

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

**arg**

## psb\_cdcpy—Copies a communication descriptor

### Syntax

call psb\_cdcpy (*desc\_out*, *desc\_a*, *info*)

#### On Entry

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

#### On Return

**desc\_out** the communication descriptor copy.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## **psb\_cdfree—Frees a communication descriptor**

### **Syntax**

call `psb_cdfree (desc_a, info)`

### **On Entry**

**desc\_a** the communication descriptor to be freed.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type `psb_desc_type`.

### **On Return**

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## psb\_cdins—Comunnication descriptor insert routine

### Syntax

call psb\_cdins (*nz*, *ia*, *ja*, *desc\_a*, *info*, *is*, *js*)

#### On Entry

**nz** the number of points being inserted.

Scope: **local**.

Type: **required**.

Specified as: an integer value.

**ia** the row indices of the points being inserted.

Scope: **local**.

Type: **required**.

Specified as: an integer array of length *nz*.

**ja** the column indices of the points being inserted.

Scope: **local**.

Type: **required**.

Specified as: an integer array of length *nz*.

**is** the row offset.

Scope: **local**.

Type: **optional**.

Specified as: an integer value.

**js** the column offset.

Scope: **local**.

Type: **optional**.

Specified as: an integer value.

#### On Return

**desc\_a** the communication descriptor to be freed.

Scope: **local**.

Type: **required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).



**info** Error code. Scope: **local**  
Type: **required**  
Specified as: an integer variable.

## psb\_cdren—Applies a reenumeration to a communication descriptor

### Syntax

call psb\_cdren (*trans*, *iperm*, *desc\_a*, *info*)

### On Entry

**trans** A character that specifies whether to permute  $A$  or  $A^T$ .

Scope: **local**

Type: **required**

Specified as: a single character with value 'N' for  $A$  or 'T' for  $A^T$ .

**iperm** An integer array containing permutation information.

Scope: **local**

Type: **required**

Specified as: an integer one-dimensional array.

**desc\_a** the communication descriptor.

Scope: **local**.

Type: **required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

### On Return

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## **psb\_spall—Allocates a sparse matrix**

### **Syntax**

call `psb_spall (a, desc_a, info, nnz)`

#### **On Entry**

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

**nnz** the number of nonzeros in the matrix.

Scope: **global**.

Type: **optional**.

Specified as: an integer value.

#### **On Return**

**a** the matrix to be allocated.

Scope:**local**

Type:**required**

Specified as: a structured data of type [psb\\_spmat\\_type](#).

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## psb\_spasb—Sparse matrix assembly routine

### Syntax

call psb\_spasb (*a*, *desc\_a*, *info*, *afmt*, *up*, *dup*)

### On Entry

**desc\_a** the communication descriptor.

Scope: **local**.

Type: **required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

**afmt** the storage format for the sparse matrix.

Scope: **global**.

Type: **optional**.

Specified as: an array of characters. If not specified 'CSR' will be assumed.

**up** ???.

Scope: **global**.

Type: **optional**.

Specified as: .

**dup** ???.

Scope: **global**.

Type: **optional**.

Specified as:

### On Return

**a** the matrix to be assembled.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_spmat\\_type](#).

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## **psb\_spcnv**—Converts a sparse matrix storage format

### **Syntax**

call `psb_spcnv (a, b, desc_a, info)`

#### **On Entry**

**a** the matrix to be converted.

Scope:**local**

Type:**required**

Specified as: a structured data of type [psb\\_spmat\\_type](#).

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

#### **On Return**

**b** the converted matrix.

Scope:**local**

Type:**required**

Specified as: a structured data of type [psb\\_spmat\\_type](#).

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## psb\_sfree—Frees a sparse matrix

### Syntax

call psb\_sfree (*a*, *desc\_a*, *info*)

### On Entry

**a** the matrix to be freed.

Scope:**local**

Type:**required**

Specified as: a structured data of type [psb\\_spmat\\_type](#).

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

### On Return

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## psb\_geins—Dense matrix insertion routine

### Syntax

call psb\_geins (*m*, *n*, *x*, *ix*, *jx*, *blk*, *desc\_a*, *info*, *iblk*, *jblk*)

#### On Entry

**m** rows number of submatrix belonging to blk to be inserted..

Scope:**local**.

Type:**required**.

Specified as: an integer value.

**n** columns number of submatrix belonging to blk to be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer value.

**ix** *x* global-row corresponding to position at which blk submatrix must be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer value.

**jx** *x* global-col corresponding to position at which blk submatrix must be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer value.

**blk** the dense submatrix to be inserted.

Scope:**local**.

Type:**required**.

Specified as: a one or two dimensional array.

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

**iblk** first row of submatrix belonging to blk to be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer value.

**jblk** first column of submatrix belonging to blk to be inserted.

Scope:**local**.

Type:**required**.

Specified as: an integer value.

### **On Return**

**x** the output dense matrix.

Scope: **local**

Type: **required**

Specified as: a one or two dimensional array.

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.



**psb\_sprn**—Reinit sparse matrix structure for psblas routines.

## Syntax

call `psb_sprn (a, desc_a, info)`

### On Entry

**a** the matrix to be reinitialized.

Scope:**local**

Type:**required**

Specified as: a structured data of type `psb_spmat_type`.

**desc\_a** the communication descriptor.

Scope:**local**.

Type:**required**.

Specified as: a structured data of type `psb_desc_type`.

### On Return

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## psb\_glob\_to\_loc—Global to local indices conversion

### Syntax

call psb\_glob\_to\_loc (*x*, *y*, *desc\_a*, *info*, *iact*)

call psb\_glob\_to\_loc (*x*, *desc\_a*, *info*, *iact*)

### On Entry

**x** An integer vector of indices to be converted.

Scope: **local**

Type: **required**

Specified as: a rank one integer array.

**desc\_a** the communication descriptor.

Scope: **local**.

Type: **required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

**iact** specifies action to be taken in case of range errors. Scope: **global**

Type: **optional**

Specified as: a character variable E, W or A.

### On Return

**x** If *y* is not present, then *x* is overwritten with the translated integer indices.

Scope: **global**

Type: **required**

Specified as: a rank one integer array.

**y** If *y* is not present, then *y* is overwritten with the translated integer indices, and *x* is left unchanged. Scope: **global**

Type: **optional**

Specified as: a rank one integer array.

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## psb\_loc\_to\_glob—Local to global indices conversion

### Syntax

call psb\_loc\_to\_glob (*x*, *y*, *desc\_a*, *info*, *iact*)

call psb\_loc\_to\_glob (*x*, *desc\_a*, *info*, *iact*)

### On Entry

**x** An integer vector of indices to be converted.

Scope: **local**

Type: **required**

Specified as: a rank one integer array.

**desc\_a** the communication descriptor.

Scope: **local**.

Type: **required**.

Specified as: a structured data of type [psb\\_desc\\_type](#).

**iact** specifies action to be taken in case of range errors. Scope: **global**

Type: **optional**

Specified as: a character variable E, W or A.

### On Return

**x** If *y* is not present, then *x* is overwritten with the translated integer indices.

Scope: **global**

Type: **required**

Specified as: a rank one integer array.

**y** If *y* is not present, then *y* is overwritten with the translated integer indices, and *x* is left unchanged. Scope: **global**

Type: **optional**

Specified as: a rank one integer array.

**info** Error code. Scope: **local**

Type: **required**

Specified as: an integer variable.

## 7 Iterative Methods

In this chapter we provide routines for preconditioners and iterative methods. Their interfaces are defined in the module `psb_methd_mod`

## psb\_cg —CG Iterative Method

This subroutine implements the CG method with restarting. The stopping criterion is the normwise backward error, in the infinity norm, i.e. the iteration is stopped when

$$\frac{\|r\|}{(\|A\|\|x\| + \|b\|)} < eps$$

or

$$\frac{\|r_i\|}{\|b\|_2} < eps$$

according to the value passed through the `istop` argument (see later).

### Syntax

```
call psb_cgs (a,prec,b,x,eps,desc_a,info,itmax,iter,err,itrace,istop)
```

#### On Entry

- a** the local portion of global sparse matrix *A*.  
Scope: **local**  
Type: **required**  
Specified as: a structured data of type [psb\\_spmat\\_type](#).
- prec** The data structure containing the preconditioner.  
Scope: **local**  
Type: **required**  
Specified as: a structured data of type [psb\\_prec\\_type](#).
- b** The RHS vector.  
Scope: **local**  
Type: **required**  
Specified as: a rank one array.
- x** The initial guess.  
Scope: **local**  
Type: **required**  
Specified as: a rank one array.

**eps** The stopping tolerance.

Scope: **global**

Type: **required**

Specified as: a real number.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**itmax** The maximum number of iterations to perform.

Scope: **global**

Type: **optional**

Default:  $itmax = 1000$ .

Specified as: an integer variable  $itmax \geq 1$ .

**itrace** A tracing parameter.

Scope: **global**

Type: **optional**

**istop** An integer specifying the stopping criterion.

Scope: **global**

Type: **optional**

## On Return

**x** The computed solution.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**iter** The number of iterations performed.

Scope: **global**

Type: **optional**

Returned as: an integer variable.

**err** The error estimate on exit.

Scope: **global**

Type: **optional**

Returned as: a real number.

**info** An error code.  
Scope: **global**  
Type: **optional**  
Returned as: an integer variable.

## psb\_cgs —CGS Iterative Method

This subroutine implements the CGS method with restarting. The stopping criterion is the normwise backward error, in the infinity norm, i.e. the iteration is stopped when

$$\frac{\|r\|}{(\|A\|\|x\| + \|b\|)} < eps$$

or

$$\frac{\|r_i\|}{\|b\|_2} < eps$$

according to the value passed through the `istop` argument (see later).

### Syntax

call `psb_cgs (a,prec,b,x,eps,desc_a,info,itmax,iter,err,itrace,istop)`

#### On Entry

**a** the local portion of global sparse matrix *A*.

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_spmat_type`.

**prec** The data structure containing the preconditioner.

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_prec_type`.

**b** The RHS vector.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**x** The initial guess.

Scope: **local**

Type: **required**

Specified as: a rank one array.



**eps** The stopping tolerance.

Scope: **global**

Type: **required**

Specified as: a real number.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**itmax** The maximum number of iterations to perform.

Scope: **global**

Type: **optional**

Default:  $itmax = 1000$ .

Specified as: an integer variable  $itmax \geq 1$ .

**itrace** A tracing parameter.

Scope: **global**

Type: **optional**

**istop** An integer specifying the stopping criterion.

Scope: **global**

Type: **optional**

## On Return

**x** The computed solution.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**iter** The number of iterations performed.

Scope: **global**

Type: **optional**

Returned as: an integer variable.

**err** The error estimate on exit.

Scope: **global**

Type: **optional**

Returned as: a real number.

**info** An error code.  
Scope: **global**  
Type: **optional**  
Returned as: an integer variable.

## psb\_bicg —BiCG Iterative Method

This subroutine implements the BiCG method with restarting. The stopping criterion is the normwise backward error, in the infinity norm, i.e. the iteration is stopped when

$$\frac{\|r\|}{(\|A\|\|x\| + \|b\|)} < eps$$

or

$$\frac{\|r_i\|}{\|b\|_2} < eps$$

according to the value passed through the `istop` argument (see later).

### Syntax

call `psb_bicg (a,prec,b,x,eps,desc_a,info,itmax,iter,err,itrace,istop)`

#### On Entry

- a** the local portion of global sparse matrix *A*.  
Scope: **local**  
Type: **required**  
Specified as: a structured data of type `psb_spmat_type`.
- prec** The data structure containing the preconditioner.  
Scope: **local**  
Type: **required**  
Specified as: a structured data of type `psb_prec_type`.
- b** The RHS vector.  
Scope: **local**  
Type: **required**  
Specified as: a rank one array.
- x** The initial guess.  
Scope: **local**  
Type: **required**  
Specified as: a rank one array.

**eps** The stopping tolerance.

Scope: **global**

Type: **required**

Specified as: a real number.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**itmax** The maximum number of iterations to perform.

Scope: **global**

Type: **optional**

Default:  $itmax = 1000$ .

Specified as: an integer variable  $itmax \geq 1$ .

**itrace** A tracing parameter.

Scope: **global**

Type: **optional**

**istop** An integer specifying the stopping criterion.

Scope: **global**

Type: **optional**

## On Return

**x** The computed solution.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**iter** The number of iterations performed.

Scope: **global**

Type: **optional**

Returned as: an integer variable.

**err** The error estimate on exit.

Scope: **global**

Type: **optional**

Returned as: a real number.

**info** An error code.  
Scope: **global**  
Type: **optional**  
Returned as: an integer variable.

## psb\_bicgstab — BiCGSTAB Iterative Method

This subroutine implements the BiCGSTAB method with restarting. The stopping criterion is the normwise backward error, in the infinity norm, i.e. the iteration is stopped when

$$\frac{\|r\|}{(\|A\|\|x\| + \|b\|)} < eps$$

or

$$\frac{\|r_i\|}{\|b\|_2} < eps$$

according to the value passed through the `istop` argument (see later).

### Syntax

call `psb_bicgstab (a,prec,b,x,eps,desc_a,info,itmax,iter,err,itrace,istop)`

#### On Entry

**a** the local portion of global sparse matrix  $A$ .

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_spmat_type`.

**prec** The data structure containing the preconditioner.

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_prec_type`.

**b** The RHS vector.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**x** The initial guess.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**eps** The stopping tolerance.

Scope: **global**

Type: **required**

Specified as: a real number.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**itmax** The maximum number of iterations to perform.

Scope: **global**

Type: **optional**

Default:  $itmax = 1000$ .

Specified as: an integer variable  $itmax \geq 1$ .

**itrace** A tracing parameter.

Scope: **global**

Type: **optional**

**istop** An integer specifying the stopping criterion.

Scope: **global**

Type: **optional**

## On Return

**x** The computed solution.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**iter** The number of iterations performed.

Scope: **global**

Type: **optional**

Returned as: an integer variable.

**err** The error estimate on exit.

Scope: **global**

Type: **optional**

Returned as: a real number.

**info** An error code.  
Scope: **global**  
Type: **optional**  
Returned as: an integer variable.



## psb\_bicgstabl — BiCGSTAB-*l* Iterative Method

This subroutine implements the BiCGSTAB-*l* method with restarting. The stopping criterion is the normwise backward error, in the infinity norm, i.e. the iteration is stopped when

$$\frac{\|r\|}{(\|A\|\|x\| + \|b\|)} < eps$$

or

$$\frac{\|r_i\|}{\|b\|_2} < eps$$

according to the value passed through the *istop* argument (see later).

### Syntax

call psb\_bicgstab (*a,prec,b,x,eps,desc\_a,info,itmax,iter,err,itrace,irst,istop*)

### On Entry

- a** the local portion of global sparse matrix *A*.  
Scope: **local**  
Type: **required**  
Specified as: a structured data of type [psb\\_spmat\\_type](#).
- prec** The data structure containing the preconditioner.  
Scope: **local**  
Type: **required**  
Specified as: a structured data of type [psb\\_prec\\_type](#).
- b** The RHS vector.  
Scope: **local**  
Type: **required**  
Specified as: a rank one array.
- x** The initial guess.  
Scope: **local**  
Type: **required**  
Specified as: a rank one array.

- eps** The stopping tolerance.  
Scope: **global**  
Type: **required**  
Specified as: a real number.
- desc\_a** contains data structures for communications.  
Scope: **local**  
Type: **required**  
Specified as: a structured data of type [psb\\_desc\\_type](#).
- itmax** The maximum number of iterations to perform.  
Scope: **global**  
Type: **optional**  
Default:  $itmax = 1000$ .  
Specified as: an integer variable  $itmax \geq 1$ .
- itrace** A tracing parameter.  
Scope: **global**  
Type: **optional**
- irst** An integer specifying the restarting iteration.  
Scope: **global**  
Type: **optional**
- istop** An integer specifying the stopping criterion.  
Scope: **global**  
Type: **optional**

## On Return

- x** The computed solution.  
Scope: **local**  
Type: **required**  
Specified as: a rank one array.
- iter** The number of iterations performed.  
Scope: **global**  
Type: **optional**  
Returned as: an integer variable.

**err** The error estimate on exit.  
Scope: **global**  
Type: **optional**  
Returned as: a real number.

**info** An error code.  
Scope: **global**  
Type: **optional**  
Returned as: an integer variable.

## psb\_gmres —GMRES Iterative Method

This subroutine implements the GMRES method with restarting. The stopping criterion is the normwise backward error, in the infinity norm, i.e. the iteration is stopped when

$$\frac{\|r\|}{(\|A\|\|x\| + \|b\|)} < eps$$

or

$$\frac{\|r_i\|}{\|b\|_2} < eps$$

according to the value passed through the `istop` argument (see later).

### Syntax

call `psb_gmres` (*a,prec,b,x,eps,desc\_a,info,itmax,iter,err,itrace,irst,istop*)

#### On Entry

**a** the local portion of global sparse matrix *A*.

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_spmat_type`.

**prec** The data structure containing the preconditioner.

Scope: **local**

Type: **required**

Specified as: a structured data of type `psb_prec_type`.

**b** The RHS vector.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**x** The initial guess.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**eps** The stopping tolerance.

Scope: **global**

Type: **required**

Specified as: a real number.

**desc\_a** contains data structures for communications.

Scope: **local**

Type: **required**

Specified as: a structured data of type [psb\\_desc\\_type](#).

**itmax** The maximum number of iterations to perform.

Scope: **global**

Type: **optional**

Default:  $itmax = 1000$ .

Specified as: an integer variable  $itmax \geq 1$ .

**itrace** A tracing parameter.

Scope: **global**

Type: **optional**

**irst** An integer specifying the restart iteration.

Scope: **global**

Type: **optional**

**istop** An integer specifying the stopping criterion.

Scope: **global**

Type: **optional**

## On Return

**x** The computed solution.

Scope: **local**

Type: **required**

Specified as: a rank one array.

**iter** The number of iterations performed.

Scope: **global**

Type: **optional**

Returned as: an integer variable.

**err** The error estimate on exit.  
Scope: **global**  
Type: **optional**  
Returned as: a real number.

**info** An error code.  
Scope: **global**  
Type: **optional**  
Returned as: an integer variable.

## 8 Preconditioner routines

PSBLAS contains the implementation of many preconditioning techniques some of which are very flexible thanks to the presence of many parameters that is possible to adjust to fit the user's needs:

- Diagonal Scaling
- Block Jacobi with ILU(0) factorization
- Additive Schwarz with the Restricted Additive Schwarz and Additive Schwarz with Harmonic extensions;
- Two-Level Additive Schwarz; this is actually a family of preconditioners since there is the possibility to choose between many variants.

## psb\_precset—Sets the preconditioner type

### Syntax

call psb\_precset (*prec*, *ptype*, *iv*, *rs*, *rv*, *ierr*)

### On Entry

**prec** Scope: **global**

Type: **required**

Specified as: e preconditioner data structure [psb\\_prec.type](#).

**ptype** the type of preconditioner. Scope: **global**

Type: **required**

Specified as: a string.

**iv** integer parameters for the preconditioner. Scope: **global**

Type: **required**

Specified as: an integer array.

**rs** Scope:

Type:

Specified as: .

**rv** Scope:

Type:

Specified as: .

**ierr** Scope:

Type:

Specified as: .



## psb\_precbld—Builds a preconditioner

### Syntax

call psb\_precbld (*a*, *desc\_a*, *prec*, *info*, *upd*)

### On Entry

**a** the system sparse matrix. Scope: **global**

Type: **required**

Specified as: a sparse matrix data structure [psb\\_spmat\\_type](#).

**desc\_a** the problem communication descriptor. Scope: **global**

Type: **required**

Specified as: a communication descriptor data structure [psb\\_desc\\_type](#).

**upd** Scope: **global**

Type: **optional**

Specified as: a character.

### On Return

**prec** the preconditioner.

Scope: **global**

Type: **required**

Specified as: a preconditioner data structure [psb\\_prec\\_type](#)

**info** the return error code.

Scope: **local**

Type: **required**

Specified as: an integer.

## psb\_precaply—Preconditioner application routine

### Syntax

call psb\_precaply (*prec,x,y,desc\_a,info,trans,work*)

### Syntax

call psb\_precaply (*prec,x,desc\_a,info,trans*)

### On Entry

**prec** the preconditioner. Scope: **global**

Type: **required**

Specified as: a preconditioner data structure [psb\\_prec\\_type](#).

**x** the source vector. Scope: **global**

Type: **require**

Specified as: a double precision array.

**desc\_a** the problem communication descriptor. Scope: **global**

Type: **required**

Specified as: a communication data structure [psb\\_desc\\_type](#).

**trans** Scope:

Type: **optional**

Specified as: a character.

**work** an optional work space Scope: **local**

Type: **optional**

Specified as: a double precision array.

### On Return

**y** the destination vector. Scope: **global**

Type: **required**

Specified as: a double precision array.

**info** the return error code.  
Scope: **local**  
Type: **required**  
Specified as: an integer.

## 9 Error handling

The PSBLAS library error handling policy has been completely rewritten in version 2.0. The idea behind the design of this new error handling strategy is to keep error messages on a stack allowing the user to trace back up to the point where the first error message has been generated. Every routine in the PSBLAS-2.0 library has, as last non-optional argument, an integer `info` variable; whenever, inside the routine, an error is detected, this variable is set to a value corresponding to a specific error code. Then this error code is also pushed on the error stack and then either control is returned to the caller routine or the execution is aborted, depending on the users choice. At the time when the execution is aborted, an error message is printed on standard output with a level of verbosity than can be chosen by the user. If the execution is not aborted, then, the caller routine checks the value returned in the `info` variable and, if not zero, an error condition is raised. This process continues on all the levels of nested calls until the level where the user decides to abort the program execution.

Figure 5 shows the layout of a generic `psb_foo` routine with respect to the PSBLAS-2.0 error handling policy. It is possible to see how, whenever an error condition is detected, the `info` variable is set to the corresponding error code which is, then, pushed on top of the stack by means of the `psb_errpush`. An error condition may be directly detected inside a routine or indirectly checking the error code returned returned by a called routine. Whenever an error is encountered, after it has been pushed on stack, the program execution skips to a point where the error condition is handled; the error condition is handled either by returning control to the caller routine or by calling the `psb\_error` routine which prints the content of the error stack and aborts the program execution.

Figure 6 reports a sample error message generated by the PSBLAS-2.0 library. This error has been generated by the fact that the user has chosen the invalid “FOO” storage format to represent the sparse matrix. From this error message it is possible to see that the error has been detected inside the `psb_cest` subroutine called by `psb_spasb ...` by process 0 (i.e. the root process).

```

subroutine psb_foo(some args, info)
  ...
  if(error detected) then
    info=errcode1
    call psb_errpush('psb_foo', errcode1)
    goto 9999
  end if
  ...
  call psb_bar(some args, info)
  if(info .ne. zero) then
    info=errcode2
    call psb_errpush('psb_foo', errcode2)
    goto 9999
  end if
  ...
9999 continue
  if (err_act .eq. act_abort) then
    call psb_error(icontxt)
    return
  else
    return
  end if

end subroutine psb_foo

```

Figure 5: The layout of a generic `psb_foo` routine with respect to PSBLAS-2.0 error handling policy.

```
=====  
Process: 0. PSBLAS Error (4010) in subroutine: df_sample  
Error from call to subroutine mat_dist  
=====  
Process: 0. PSBLAS Error (4010) in subroutine: mat_distv  
Error from call to subroutine psb_spasb  
=====  
Process: 0. PSBLAS Error (4010) in subroutine: psb_spasb  
Error from call to subroutine psb_cest  
=====  
Process: 0. PSBLAS Error (136) in subroutine: psb_cest  
Format F00 is unknown  
=====  
Aborting...
```

Figure 6: A sample PSBLAS-2.0 error message. Process 0 detected an error condition inside the psb\_cest subroutine

## **psb\_errpush—Pushes an error code onto the error stack**

### **Syntax**

call psb\_errpush (*err\_c*, *r\_name*, *i\_err*, *a\_err*)

### **On Entry**

**err\_c** the error code

Scope: **local**

Type: **required**

Specified as: an integer.

**r\_name** the routine where the error has been caught.

Scope: **local**

Type: **required**

Specified as: a string.

**i\_err** additional info for error code

Scope: **local**

Type: **optional**

Specified as: an integer array

**a\_err** additional info for error code

Scope: **local**

Type: **optional**

Specified as: a string.

**psb\_error**—Prints the error stack content and aborts execution

## Syntax

call `psb_error` (*icontxt*)

### On Entry

**icontxt** the communication context.

Scope: **global**

Type: **optional**

Specified as: an integer.



**psb\_set\_errverbosity**—Sets the verbosity of error messages.

## Syntax

call psb\_set\_errverbosity (*v*)

### On Entry

**v** the verbosity level  
Scope: **global**  
Type: **required**  
Specified as: an integer.

**psb\_set\_erraction**—Set the type of action to be taken upon error condition.

## Syntax

```
call psb_set_erraction (err_act)
```

### On Entry

**err\_act** the type of action.

Scope: **global**

Type: **required**

Specified as: an integer.

## psb\_errcomm—Error communication routine

### Syntax

call psb\_errcomm (*icontxt*, *err*)

### On Entry

**icontxt** the communication context.

Scope: **global**

Type: **required**

Specified as: an integer.

**err** the error code to be communicated

Scope: **global**

Type: **required**

Specified as: an integer.